

PicoScope 5000 Series (A API) PC Oscilloscopes

Programmer's Guide



Contents

1 Introduction	1
1 Overview	1
2 Minimum PC requirements	2
3 License agreement	3
2 Programming the 5000 Series oscilloscopes	4
3 The ps5000a driver	5
4 System requirements	6
5 Voltage ranges	7
6 Triggering	8
7 Sampling modes	9
1 Block mode	
1 Using block mode	11
2 Asynchronous calls in block mode	
1 Using rapid block mode	
2 Rapid block mode example 1: no aggregation	14
3 Rapid block mode example 2: using aggregation	16
3 ETS (Equivalent Time Sampling)	
1 Using ETS mode 4 Streaming mode	
1 Using streaming mode	
5 Retrieving stored data	
8 Timebases	21
9 Power options	22
10 Combining several oscilloscopes	23
11 API functions	24
1 ps5000aBlockReady (callback)	
2 ps5000aChangePowerSource	
3 ps5000aCloseUnit	
4 ps5000aCurrentPowerSource	
5 ps5000aDataReady (callback)	
6 ps5000aEnumerateUnits	
7 ps5000aFlashLed	
8 ps5000aGetAnalogueOffset	
9 ps5000aGetChannelInformation	
10 ps5000aGetDeviceResolution	33

11 ps5000aGetMaxDownSampleRatio	36
12 ps5000aGetMaxSegments	37
13 ps5000aGetNoOfCaptures	38
14 ps5000aGetNoOfProcessedCaptures	39
15 ps5000aGetStreamingLatestValues	40
16 ps5000aGetTimebase	41
17 ps5000aGetTimebase2 ·····	42
18 ps5000aGetTriggerTimeOffset	43
19 ps5000aGetTriggerTimeOffset64	44
20 ps5000aGetUnitInfo	45
21 ps5000aGetValues	
1 Downsampling modes	
22 ps5000aGetValuesAsync	
23 ps5000aGetValuesBulk	
24 ps5000aGetValuesOverlapped	
25 ps5000aGetValuesOverlappedBulk	
26 ps5000aGetValuesTriggerTimeOffsetBulk	
27 ps5000aGetValuesTriggerTimeOffsetBulk64	
28 ps5000alsReady	56
29 ps5000alsTriggerOrPulseWidthQualifierEnabled	
30 ps5000aMaximumValue	
31 ps5000aMemorySegments	59
32 ps5000aMinimumValue	
33 ps5000aNoOfStreamingValues	61
34 ps5000aOpenUnit	62
35 ps5000aOpenUnitAsync	63
36 ps5000aOpenUnitProgress	64
37 ps5000aPingUnit	65
38 ps5000aRunBlock	66
39 ps5000aRunStreaming	68
40 ps5000aSetBandwidthFilter	70
41 ps5000aSetChannel	71
42 ps5000aSetDataBuffer	73
43 ps5000aSetDataBuffers	74
44 ps5000aSetDeviceResolution	75
45 ps5000aSetEts	76
46 ps5000aSetEtsTimeBuffer	77
47 ps5000aSetEtsTimeBuffers	78
48 ps5000aSetNoOfCaptures	79
49 ps5000aSetPulseWidthQualifier	80
1 ps5000a_PWQ_CONDITIONS structure	
50 ps5000aSetSigGenArbitrary	83
1 AWG index modes	
51 ps5000aSetSigGenBuiltIn	
52 ns5000aSetSigGenPropertiesArbitrary	90


	0.1
53 ps5000aSetSigGenPropertiesBuiltIn	
54 ps5000aSetSimpleTrigger	92
55 ps5000aSetTriggerChannelConditions	93
1 PS5000A_TRIGGER_CONDITIONS structure	94
56 ps5000aSetTriggerChannelDirections	95
57 ps5000aSetTriggerChannelProperties	96
1 PS5000A_TRIGGER_CHANNEL_PROPERTIES structure ·····	97
58 ps5000aSetTriggerDelay	
59 ps5000aSigGenArbitraryMinMaxValues	99
60 ps5000aSigGenFrequencyToPhase	100
61 ps5000aSigGenSoftwareControl	
62 ps5000aStop	
63 ps5000aStreamingReady (callback)	
12 Programming examples	104
13 Driver status codes	105
14 Enumerated types and constants	110
15 Numeric data types	111
16 Glossary	112
Index	115



1 Introduction

1.1 Overview

The PicoScope 5000 A and B Series PC Oscilloscopes from Pico Technology are a range of high-specification, real-time measuring instruments that connect to the USB port of your computer. The series covers various options of portability, deep memory, fast sampling rates and high bandwidth, making it a highly versatile range that suits a wide range of applications. The oscilloscopes are all hispeed USB 2.0 devices, also compatible with USB 1.1 and USB 3.0.



This manual explains how to use the API (application programming interface) functions, so that you can develop your own programs to collect and analyze data from the oscilloscope.

The information in this manual applies to the following oscilloscopes:

PicoScope 5242A PicoScope 5243A PicoScope 5244A PicoScope 5442A PicoScope 5443A PicoScope 5444A	The A models are high speed portable oscilloscopes, with a function generator.
PicoScope 5242B PicoScope 5243B PicoScope 5244B PicoScope 5442B PicoScope 5443B PicoScope 5444B	The B models are as the A models, but feature an arbitrary waveform generator and deeper memory.

For information on any PicoScope 5000 Series oscilloscope, refer to the documentation on our <u>website</u>.

2 Introduction

1.2 Minimum PC requirements

To ensure that your PicoScope 5000 Series Oscilloscope operates correctly, you must have a computer with at least the minimum system requirements as shown in the following table. The performance of the oscilloscope will be better with a more powerful PC, and will benefit from a multi-core processor. Please note the PicoScope software is not installed as part of the SDK.

Item	Absolute minimum	Recommended minimum	Recommended full specification
Operating system	Windows XP SP3 Windows Vista Windows 7 Windows 8*		
	32 bit and 64** bit versions supported		
Processor		1 GHz	1 GHz
Memory	As required	512 MB	512 MB
Free disk space***	by Windows	32-bit: 600 MB 64-bit: 1.5 GB	32-bit: 850 MB 64-bit: 2 GB
Ports	USB 1.1 compliant port	USB 2.0 or 3.0	compliant port

^{*} Not Windows RT.

^{**} While the driver will run on a 64 bit operating system, the driver itself is 32 bit, and therefore will run as a 32 bit.

^{***} The PicoScope software does not use all the disk space specified in the table. The free space is required to make Windows run efficiently.

1.3 License agreement

Grant of license. The material contained in this release is licensed, not sold. Pico Technology Limited ('Pico') grants a license to the person who installs this software, subject to the conditions listed below.

Access. The licensee agrees to allow access to this software only to persons who have been informed of and agree to abide by these conditions.

Usage. The software in this release is for use only with Pico products or with data collected using Pico products.

Copyright. The software in this release is for use only with Pico products or with data collected using Pico products. You may copy and distribute the SDK without restriction, as long as you do not remove any Pico Technology copyright statements. The example programs in the SDK may be modified, copied and distributed for the purpose of developing programs to collect data using Pico products.

Liability. Pico and its agents shall not be liable for any loss or damage, howsoever caused, related to the use of Pico equipment or software, unless excluded by statute.

Fitness for purpose. No two applications are the same, so Pico cannot guarantee that its equipment or software is suitable for a given application. It is therefore the user's responsibility to ensure that the product is suitable for the user's application.

Mission-critical applications. Because the software runs on a computer that may be running other software products, and may be subject to interference from these other products, this license specifically excludes usage in 'mission-critical' applications, for example life-support systems.

Viruses. This software was continuously monitored for viruses during production. However, the user is responsible for virus checking the software once it is installed.

Support. No software is ever error-free, but if you are dissatisfied with the performance of this software, please contact our technical support staff.

Upgrades. We provide upgrades, free of charge, from our web site at www.picotech.com. We reserve the right to charge for updates or replacements sent out on physical media.

Trademarks. Windows is a trademark or registered trademark of Microsoft Corporation. Pico Technology Limited and PicoScope are internationally registered trademarks.

2 Programming the 5000 Series oscilloscopes

The ps5000a.dll dynamic link library in your PicoScope installation directory allows you to program a PicoScope 5000 Series (A API) oscilloscope using standard C $\underline{\text{function calls.}}$

A typical program for capturing data consists of the following steps:

- Open the scope unit.
- Set up the input channels with the required voltage ranges and coupling type.
- Set up triggering.
- Start capturing data. (See <u>Sampling modes</u>, where programming is discussed in more detail.)
- Wait until the scope unit is ready.
- Stop capturing data.
- Copy data to a buffer.
- Close the scope unit.

Numerous <u>sample programs</u> are included in the SDK. These demonstrate how to use the functions of the driver software in each of the modes available.

3 The ps5000a driver

Your application will communicate with a driver called ps5000a.dl1. This driver is used by all the 5000 A/B Series oscilloscopes (but not the PicoScope 5203 and 5204). The driver exports the PicoScope 5000 function definitions in standard C format, but this does not limit you to programming in C: you can use the API with any programming language that supports standard C calls.

The API driver depends on another DLL, PicoIpp.dll, and a low-level driver, WinUsb.sys. These are installed by the SDK when you plug the oscilloscope into the computer for the first time. Your application does not call these drivers directly.

6 System requirements

4 System requirements

General requirements

See Minimum PC requirements.

USB

The PicoScope 5000A driver offers <u>four different methods</u> of recording data, all of which support both USB 1.1, USB 2.0, and USB 3.0 connections. The 5000 A and B Series oscilloscopes are all hi-speed USB 2.0 devices, so transfer rate will not increase by using USB 3.0, but it will decrease when using USB 1.1.

5 Voltage ranges

You can set a device input channel to any voltage range from ± 10 mV to ± 20 V with the <u>ps5000aSetChannel</u> function. Each sample is scaled to 16 bits so that the values returned to your application are as follows:

Function	Voltage	Value returned	
		decimal	hex
8-bit			
ps5000aMinimumValue	minimum	-32 512	8100
	zero	0	0000
ps5000aMaximumValue	maximum	+32 512	7F00
12, 14, 15 and 16-bit			
ps5000aMinimumValue	minimum	-32 767	8001
	zero	0	0000
ps5000aMaximumValue	maximum	+32 767	7FFF

You can determine the minimum and maximum scaled values for the currently selected resolution using the <u>ps5000aMinimumValue</u> and <u>ps5000aMaximumValue</u> function calls.

8 Triggering

6 Triggering

PicoScope 5000 Series oscilloscopes can either start collecting data immediately, or be programmed to wait for a **trigger** event to occur. In both cases you need to use the PicoScope 5000 trigger function ps5000aSetTriggerChannelConditions, ps5000aSetTriggerChannelDirections and ps5000aSetTriggerChannelProperties (these can also be called individually, rather than using ps5000aSetSimpleTrigger in order to set up advanced trigger types such as pulse width). A trigger event can occur when one of the signal or trigger input channels crosses a threshold voltage on either a rising or a falling edge.

PicoScope 5000 Series oscilloscopes can run in various **sampling modes**.

- Block mode. In this mode, the scope stores data in its buffer memory and then transfers it to the PC. When the data has been collected it is possible to examine the data, with an optional downsampling factor. The data is lost when a new run is started in the same segment, the settings are changed, or the scope is powered down.
- **ETS mode.** In this mode, it is possible to increase the effective sampling rate of the scope when capturing repetitive signals. It is a modified form of block mode.
- Rapid block mode. This is a variant of block mode that allows you to capture more than one waveform at a time with a minimum of delay between captures. You can use downsampling in this mode if you wish.
- Streaming mode. In this mode, data is passed directly to the PC without entire blocks being stored in the scope's buffer memory. This enables long periods of slow data collection for chart recorder and data-logging applications. Streaming mode supports downsampling and triggering, while providing fast streaming at up to:

8-bit mode

- 7.8125 MS/s (128 ns per sample) when three or four channels are active
- 15.625 MS/s (64 ns per sample) when two channels are active
- 31.25 MS/s (32 ns per sample) when one channel is active

12, 14, 15, and 16-bit modes*

- 3.906 MS/s (256 ns per sample) when three or four channels are active
- 7.8125 MS/s (128 ns per sample) when two channels are active
- 15.625 MS/s (64 ns per sample) when one channel is active
- * 15-bit mode supports a maximum of two channels. 16-bit mode supports only one channel.

In all sampling modes, the driver returns data asynchronously using a <u>callback</u>. This is a call to one of the functions in your own application. When you request data from the scope, you pass to the driver a pointer to your callback function. When the driver has written the data to your buffer, it makes a callback (calls your function) to signal that the data is ready. The callback function then signals to the application that the data is available.

Because the callback is called asynchronously from the rest of your application, in a separate thread, you must ensure that it does not corrupt any global variables while it runs.

For compatibility of programming environments not supporting callback, polling of the driver is available in block mode.

Note: The Oversampling feature has been replaced by PS5000A_RATIO_MODE_AVERAGE.

7.1 Block mode

In **block mode**, the computer prompts a PicoScope 5000 Series oscilloscope to collect a block of data into its internal memory. When the oscilloscope has collected the whole block, it signals that it is ready and then transfers the whole block to the computer's memory through the USB port.

- Block size. The maximum number of values depends upon the size of the oscilloscope's memory. The memory buffer is shared between the enabled channels, so if two channels are enabled, each receives half the memory. These features are handled transparently by the driver. The block size also depends on the number of memory segments in use (see pss5000aMemorySegments).
- Sampling rate. A PicoScope 5000 Series oscilloscope can sample at a number of different rates according to the selected <u>timebase</u> and the combination of channels that are enabled. See the <u>PicoScope 5000 Series User's Guide</u> for the specifications that apply to your scope model.
- **Setup time.** The driver normally performs a number of setup operations, which can take up to 50 milliseconds, before collecting each block of data. If you need to collect data with the minimum time interval between blocks, use rapid block mode and avoid calling setup functions between calls to ps5000aRunBlock, ps5000aStop and ps5000aGetValues.
- Downsampling. When the data has been collected, you can set an optional downsampling factor and examine the data. Downsampling is a process that reduces the amount of data by combining adjacent samples. It is useful for zooming in and out of the data without having to repeatedly transfer the entire contents of the scope's buffer to the PC.
- Segmented memory. The scope's internal memory can be divided into segments so that you can capture several waveforms in succession. Configure this using ps5000aMemorySegments.
- **Data retention.** The data is lost when a new run is started in the same segment, the settings are changed, or the scope is powered down or the power source is changed (for flexible power devices).


See <u>Using block mode</u> for programming details.

7.1.1 Using block mode

You can use <u>block mode</u> with or without <u>aggregation</u>. With aggregation, you need to set up two buffers for each channel to receive the minimum and maximum values, see <u>rapid block mode example 1</u> for an example of using <u>aggregation</u>.

The below is the general procedure for reading and displaying data in <u>block mode</u> using a single <u>memory segment:</u>

- 1. Open the oscilloscope using ps5000aOpenUnit.
- 2. Select channel ranges and AC/DC coupling using ps5000aSetChannel.
- 3. Using <u>ps5000aGetTimebase</u>, select timebases until the required nanoseconds per sample is located.
- 4. Use the trigger setup functions <u>ps5000aSetTriggerChannelDirections</u> and <u>ps5000aSetTriggerChannelProperties</u> to set up the trigger if required.
- 5. Start the oscilloscope running using ps5000aRunBlock.
- 6. Wait until the oscilloscope is ready using the <u>ps5000aBlockReady</u> callback (or poll using <u>ps5000aIsReady</u>).
- 7. Use <u>ps5000aSetDataBuffer</u> to tell the driver where your memory buffer is.
- 8. Transfer the block of data from the oscilloscope using ps5000aGetValues.
- 9. Display the data.
- 10. Stop the oscilloscope using ps5000aStop.
- 11. Repeat steps 5 to 9.



12. Request new views of stored data using different downsampling parameters: see Retrieving stored data.

7.1.2 Asynchronous calls in block mode

The ps5000aGetValues function may take a long time to complete if a large amount of data is being collected. For example, it can take 14 seconds (or several minutes on USB 1.1) to retrieve the full 512 Msamples (in 8-bit mode) from a PicoScope 5444B using a USB 2.0 connection. To avoid hanging the calling thread, it is possible to call ps5000aGetValuesAsync instead. This immediately returns control to the calling thread, which then has the option of waiting for the data or calling ps5000aStop to abort the operation.

7.2 Rapid block mode

In normal <u>block mode</u>, the PicoScope 5000 series scopes collect one waveform at a time. You start the the device running, wait until all samples are collected by the device, and then download the data to the PC or start another run. There is a time overhead of tens of milliseconds associated with starting a run, causing a gap between waveforms. When you collect data from the device, there is another minimum time overhead which is most noticeable when using a small number of samples.

Rapid block mode allows you to sample several waveforms at a time with the minimum time between waveforms. It reduces the gap from milliseconds to less than 2 microseconds (on fastest timebase).

See Using rapid block mode for details.

7.2.1 Using rapid block mode

You can use <u>rapid block mode</u> with or without <u>aggregation</u>. With aggregation, you need to set up two buffers for each channel to receive the minimum and maximum values.

Without aggregation

- 1. Open the oscilloscope using ps5000aOpenUnit.
- 2. Select channel ranges and AC/DC coupling using ps5000aSetChannel.
- 3. Using <u>ps5000aGetTimebase</u>, select timebases until the required nanoseconds per sample is located.
- 4. Use the trigger setup functions <u>ps5000aSetTriggerChannelDirections</u> and <u>ps5000aSetTriggerChannelProperties</u> to set up the trigger if required.
- 5. Set the number of memory segments equal to or greater than the number of captures required using ps5000aSetNoOfCaptures before each run to specify the number of waveforms to capture.
- 6. Start the oscilloscope running using <u>ps5000aRunBlock</u>. THEN EITHER
- 7a. To obtain data before rapid block capture has finished, call <u>ps5000aStop</u> and then <u>ps5000aGetNoOfCaptures</u> to find out how many captures were completed. OR
- 7b. Wait until the oscilloscope is ready using ps5000aIsReady.
 OR
- 7c. Wait on the callback function.
- 8. Use <u>ps5000aSetDataBuffer</u> to tell the driver where your memory buffers are.
- 9. Transfer the blocks of data from the oscilloscope using <u>ps5000aGetValuesBulk</u> (or <u>ps5000aGetValues</u> to retrieve one buffer at a time). These functions stop the oscilloscope.
- 10. Retrieve the time offset for each data segment using ps5000aGetValuesTriggerTimeOffsetBulk64.
- 11. Display the data.
- 12. Repeat steps 6 to 11 if necessary.
- 13. Call <u>ps5000aStop</u> (usually unnecessary as the scope stops automatically in most cases, but recommended as a precaution).

With aggregation

To use rapid block mode with aggregation, follow steps 1 to 7 above, then proceed as follows:

- 8a. Call <u>ps5000aSetDataBuffer</u> or (<u>ps5000aSetDataBuffers</u>) to set up one pair of buffers for every waveform segment required.
- 9a. Call <u>ps5000aGetValuesBulk</u> for each pair of buffers.
- 10a. Retrieve the time offset for each data segment using ps5000aGetValuesTriggerTimeOffsetBulk64.

Continue from step 11 above.

7.2.2 Rapid block mode example 1: no aggregation

```
#define MAX_SAMPLES 1000
```

Set up the device up as usual.

- Open the device
- Channels
- Trigger
- Number of memory segments (this should be equal or more than the no of captures required)

Comment: these variables have been set as an example and can be any valid value. pParameter will be set true by your callback function lpReady.

```
while (!pParameter) Sleep (0);
for (int i = 0; i < 10; i++)
{
   for (int c = PS5000A_CHANNEL_A; c <= PS5000A_CHANNEL_B; c++)
   {
     ps5000aSetDataBuffer
      (
        handle,
        c,
        &buffer[c][i],
        MAX_SAMPLES,
        i
        PS5000A_RATIO_MODE_NONE
     );
   }
}</pre>
```

Comments: buffer has been created as a two-dimensional array of pointers to shorts, which will contain 1000 samples as defined by MAX_SAMPLES. There are only 10 buffers set, but it is possible to set up to the number of captures you have requested.

PS5000A_RATIO_MODE_NONE can be substituted for PS5000A_RATIO_MODE_AGGREGATE,
PS5000A_RATIO_MODE_DECIMATE, or PS5000A_RATIO_MODE_AVERAGE.

Comments: the number of samples could be up to noOfPreTriggerSamples + noOfPostTriggerSamples, the values set in ps5000aRunBlock. The samples are always returned from the first sample taken, unlike the ps5000aGetValues function which allows the sample index to be set. The above segments start at 10 and finish at 19 inclusive. It is possible for the fromSegmentIndex to wrap around to the toSegmentIndex, by setting the fromSegmentIndex to 98 and the toSegmentIndex to 7.

```
ps5000aGetValuesTriggerTimeOffsetBulk64
(
   handle,
   times,
   timeUnits,
   10,
   19
)
```

Comments: the above segments start at 10 and finish at 19 inclusive. It is possible for the fromSegmentIndex to wrap around to the toSegmentIndex, if the fromSegmentIndex is set to 98 and the toSegmentIndex to 7.

7.2.3 Rapid block mode example 2: using aggregation

```
#define MAX_SAMPLES 1000
```

Set up the device up as usual.

- Open the device
- Channels
- Trigger
- Number of memory segments (this should be equal or more than the number of captures required)

Comments: the set-up for running the device is exactly the same whether or not aggregation will be used when you retrieve the samples.

```
for (int segment = 10; segment < 20; segment++)
{
for (int c = PS5000A_CHANNEL_A; c <= PS5000A_CHANNEL_D; c++)
{
   ps5000aSetDataBuffers
   (
     handle,
     c,
     &bufferMax[c],
     &bufferMin[c]
     MAX_SAMPLES
     Segment,
     PS5000A_RATIO_MODE_AGGREGATE
   );
}</pre>
```

Comments: since only one waveform will be retrieved at a time, you only need to set up one pair of buffers; one for the maximum samples and one for the minimum samples. Again, the buffer sizes are 1000 samples.

```
ps5000aGetValues
    handle,
    0,
    &noOfSamples, // set to MAX_SAMPLES on entering
    1000,
    &downSampleRatioMode, //set to RATIO MODE AGGREGATE
    index.
    overflow
  );
  ps5000aGetTriggerTimeOffset64
    handle,
    &time,
    &timeUnits,
    index
  )
}
```

Comments: each waveform is retrieved one at a time from the driver with an aggregation of 1000.

7.3 ETS (Equivalent Time Sampling)

ETS is a way of increasing the effective sampling rate of the scope when capturing repetitive signals. It is a modified form of <u>block mode</u>, and is controlled by the ps5000a set of trigger functions and the <u>ps5000aSetEts</u> function.


- Overview. ETS works by capturing several cycles of a repetitive waveform, then combining them to produce a composite waveform that has a higher effective sampling rate than the individual captures. The scope hardware accurately measures the delay, which is a small fraction of a single sampling interval, between each trigger event and the subsequent sample. The driver then shifts each capture slightly in time and overlays them so that the trigger points are exactly lined up. The result is a larger set of samples spaced by a small fraction of the original sampling interval. The maximum effective sampling rates that can be achieved with this method are listed in the User's Guide for the scope device.
- **Trigger stability.** Because of the high sensitivity of ETS mode to small time differences, the trigger must be set up to provide a stable waveform that varies as little as possible from one capture to the next.
- **Callback.** ETS mode calls the <u>ps5000aBlockReady</u> callback function when a new waveform is ready for collection. The <u>ps5000aGetValues</u> function needs to be called for the waveform to be retrieved.

Applicability	Available in <u>block mode</u> only.
	Not suitable for one-shot (non-repetitive) signals.
	Aggregation is not supported.
	Edge-triggering only.
	Auto trigger delay (autoTriggerMilliseconds) is ignored.

7.3.1 Using ETS mode

This is the general procedure for reading and displaying data in <u>ETS mode</u> using a single memory segment:

- 1. Open the oscilloscope using ps5000aOpenUnit.
- 2. Select channel ranges and AC/DC coupling using ps5000aSetChannel.
- 3. Use ps5000aSetEts to enable ETS and to set the parameters.
- 3. Using <u>ps5000aGetTimebase</u>, select timebases until the required nanoseconds per sample is located.
- 4. Use the trigger setup functions <u>ps5000aSetTriggerChannelDirections</u> and <u>ps5000aSetTriggerChannelProperties</u> to set up the trigger.
- 5. Start the oscilloscope running using ps5000aRunBlock.
- 6. Wait until the oscilloscope is ready using the <u>ps5000aBlockReady</u> callback (or poll using <u>ps5000aIsReady</u>).
- 7. Use <u>ps5000aSetDataBuffer</u> to tell the driver where your memory buffer is.
- 8. Transfer the block of data from the oscilloscope using ps5000aGetValues.
- 9. Display the data.
- 10. While you want to collect updated captures, repeat steps 6-9.
- 11. Stop the oscilloscope using <u>ps5000aStop</u>.
- 12. Repeat steps 5 to 11.



7.4 Streaming mode

Streaming mode can capture data without the gaps that occur between blocks when using block mode. Streaming mode supports downsampling and triggering, while providing fast streaming at up to 31.25 MS/s (32 ns per sample) when one channel is active, depending on the computer's performance. This makes it suitable for **high-speed data acquisition**, allowing you to capture long data sets limited only by the computer's memory.


- Aggregation. The driver returns aggregated readings while the device is streaming. If aggregation is set to 1 then only one buffer is used per channel. When aggregation is set above 1 then two buffers (maximum and minimum) per channel are used.
- **Memory segmentation.** The memory can be divided into <u>segments</u> to reduce the latency of data transfers to the PC. However, this increases the risk of losing data if the PC cannot keep up with the device's sampling rate.

See <u>Using streaming mode</u> for programming details.

7.4.1 Using streaming mode

This is the general procedure for reading and displaying data in <u>streaming mode</u> using a single <u>memory segment</u>:


- 1. Open the oscilloscope using ps5000aOpenUnit.
- 2. Select channels, ranges and AC/DC coupling using ps5000aSetChannel.
- 3. Use the trigger setup functions <u>ps5000aSetTriggerChannelDirections</u> and <u>ps5000aSetTriggerChannelProperties</u> to set up the trigger if required.
- 4. Call ps5000aSetDataBuffer to tell the driver where your data buffer is.
- 5. Set up aggregation and start the oscilloscope running using ps5000aRunStreaming.
- 6. Call ps5000aGetStreamingLatestValues to get data.
- 7. Process data returned to your application's function. This example is using Auto Stop, so after the driver has received all the data points requested by the application, it stops the device streaming.
- 8. Call ps5000aStop, even if Auto Stop is enabled.



9. Request new views of stored data using different downsampling parameters: see Retrieving stored data.

7.5 Retrieving stored data

You can collect data from the PicoScope 5000A driver with a different <u>downsampling</u> factor when <u>ps5000aRunBlock</u> or <u>ps5000aRunStreaming</u> has already been called and has successfully captured all the data. Use <u>ps5000aGetValuesAsync</u>.



8 Timebases

The API allows you to select any of 2^{32} different timebases. The timebases allow slow enough sampling in block mode to overlap the streaming sample intervals, so that you can make a smooth transition between block mode and streaming mode. Calculate the timebase using the <u>ps5000aGetTimebase</u> call. Accepted timebases for each resolution mode are:

8-bit resolution

Timebase	Sample interval formula	Sample interval examples
0 to 2	2 ^{timebase} / 1,000,000,000	0 => 1 ns
		1 => 2 ns
		2 => 4 ns
3 to 2 ³² –1	(timebase-2) / 125,000,000	3 => 8 ns
		$2^{32}-1 = > \sim 34.36 \text{ s}$

12-bit resolution

Timebase*	Sample interval formula	Sample interval examples
1 to 3	2 ^(timebase-1) / 500,000,000	1 => 2 ns
		2 => 4 ns
		3 => 8 ns
4 to 2 ³² –2	(timebase-3) / 62,500,000	4 => 16 ns
		$2^{32}-2 => \sim 68.72 \text{ s}$

14, 15-bit resolutions

Timebase†	Sample interval formula	Sample interval examples
3 to 2 ³² –1	(timebase-2) / 125,000,000	3 => 8 ns 4 => 16 ns 5 => 24 ns
		$2^{32}-1 = > \sim 34.36 \text{ s}$

16-bit resolution

Timebase#	Sample interval formula	Sample interval examples
4 to 2 ³² –2	(timebase-3) / 62,500,000	4 => 16 ns 5 => 32 ns 6 => 48 ns
		2^{32} -2 => ~ 68.72 s

^{*}Timebase 0 is not available in 12-bit resolution mode.

[†]Timebases 0, 1 and 2 are not available in 14 and 15-bit resolution modes.

[‡]Timebases 0, 1, 2 and 3 are not available in 16-bit resolution mode.

22 Power options

9 Power options

The 4-channel 5000 Series oscilloscopes allow you to choose from two different methods of powering your device. Our flexible power feature offers the choice of powering your device using a single-headed USB cable and provided power supply unit, or using our double-headed USB cable to draw power from two powered USB ports for use in 2-channel mode. If the power source is changed (i.e. AC adaptor being connected or disconnected) while the oscilloscope is in operation, the oscilloscope will restart automatically and any unsaved data will be lost.

For further information on these options, refer to the documentation included with your device.

Power options functions

The following functions support the flexible power feature:

- ps5000aChangePowerSource
- ps5000aCurrentPowerSource

If you want the device to run on USB power only, instruct the driver by calling ps5000aChangePowerSource after calling ps5000aOpenUnit. If ps5000aOpenUnit is called without the power supply connected, the driver returns PICO_POWER_SUPPLY_NOT_CONNECTED. If the supply is connected or disconnected during use, the driver will return the relevant status code and you must then call ps5000aChangePowerSource to continue running the scope.

10 Combining several oscilloscopes

It is possible to collect data using up to 64 PicoScope 5000 Series oscilloscopes at the same time, depending on the capabilities of the PC. Each oscilloscope must be connected to a separate USB port. The ps5000aOpenUnit function returns a handle to an oscilloscope. All the other functions require this handle for oscilloscope identification. For example, to collect data from two oscilloscopes at the same time:

```
CALLBACK ps5000aBlockReady(...)
// define callback function specific to application
handle1 = ps5000aOpenUnit()
handle2 = ps5000aOpenUnit()
ps5000aSetChannel(handle1)
// set up unit 1
ps5000aRunBlock(handle1)
ps5000aSetChannel(handle2)
// set up unit 2
ps5000aRunBlock(handle2)
// data will be stored in buffers
// and application will be notified using callback
ready = FALSE
while not ready
   ready = handle1 ready
   ready &= handle2_ready
```

24 API functions

11 API functions

The PicoScope 5000A Series API exports the following functions for you to use in your own applications. All functions are C functions using the standard call naming convention (__stdcall). They are all exported with both decorated and undecorated names.

<u>ps5000aBlockReady</u> indicate when block-mode data ready ps5000aChangePowerSource configures the unit's power source

<u>ps5000aCloseUnit</u> close a scope device

<u>ps5000aCurrentPowerSource</u> indicate the current power state of the device ps5000aDataReady indicate when post-collection data ready

ps5000aEnumerateUnits find all connected oscilloscopes ps5000aFlashLed flash the front-panel LED

<u>ps5000aFiashLed</u> flash the front-panel LED query the permitted analog offset range

<u>ps5000aGetChannelInformation</u> queries which ranges are available on a device <u>ps5000aGetDeviceResolution</u> retrieves the resolution specified device will run

<u>ps5000aGetMaxDownSampleRatio</u> query the aggregation ratio for data <u>ps5000aGetMaxSegments</u> query the maximum number of segments

ps5000aGetNoOfCaptures find out how many captures are available ps5000aGetNoOfProcessedCaptures query number of captures processed

ps5000aGetStreamingLatestValues

get streaming data while scope running

find out what time become are published.

ps5000aGetTimebase find out what timebases are available find out what timebases are available ps5000aGetTimebase2 find out what timebases are available find out when trigger occurred (23 bit)

<u>ps5000aGetTriggerTimeOffset</u> find out when trigger occurred (32-bit) <u>ps5000aGetTriggerTimeOffset64</u> find out when trigger occurred (64-bit)

ps5000aGetUnitInfo read information about scope device ps5000aGetValues retrieve block-mode data with callback ps5000aGetValuesAsync retrieve streaming data with callback ps5000aGetValuesBulk retrieve data in rapid block mode

<u>ps5000aGetValuesOverlapped</u>
<u>ps5000aGetValuesOverlappedBulk</u>
set up data collection ahead of capture
set up data collection in rapid block mode

ps5000aGetValuesTriggerTimeOffsetBulk get rapid-block waveform timings (32-bit)

<u>ps5000aGetValuesTriggerTimeOffsetBulk64</u> get rapid-block waveform timings (64-bit) ps5000aIsReady get rapid-block mode

ps5000aIsTriggerOrPulseWidthQualifierEnabled find out whether trigger is enabled

<u>ps5000aMaximumValue</u> query the max. ADC count in GetValues calls divide scope memory into segments

<u>ps5000aMinimumValue</u> query the min. ADC count in GetValues calls <u>ps5000aNoOfStreamingValues</u> get number of samples in streaming mode

ps5000aOpenUnit open a scope device

<u>ps5000aOpenUnitAsync</u> open a scope device without waiting <u>ps5000aOpenUnitProgress</u> check progress of OpenUnit call

ps5000aPingUnitcheck communication with deviceps5000aRunBlockstart block modeps5000aRunStreamingstart streaming mode

<u>ps5000aSetBandwidthFilter</u> specifies the bandwidth limit <u>ps5000aSetChannel</u> set up input channels

ps5000aSetDataBufferregister data buffer with driverps5000aSetDataBuffersregister aggregated data buffers with driverps5000aSetDeviceResolutionsets the resolution a specified device will run

ps5000aSetEts set up equivalent-time sampling

ps5000aSetEtsTimeBuffer set up buffer for ETS timings (64-bit)
ps5000aSetEtsTimeBuffers set up buffer for ETS timings (32-bit)

<u>ps5000aSetNoOfCaptures</u>
set number of captures to collect in one run
<u>ps5000aSetPulseWidthQualifier</u>
set up pulse width triggering

ps5000aSetSigGenArbitrary set up arbitrary waveform generator set up standard signal generator

ps5000aSetSigGenPropertiesArbitrary change AWG settings

<u>ps5000aSetSigGenPropertiesBuiltIn</u> change function generator settings <u>ps5000aSetSimpleTrigger</u> set up level triggers only

ps5000aSetTriggerChannelConditions specify which channels to trigger on ps5000aSetTriggerChannelDirections set up signal polarities for triggering

<u>ps5000aSetTriggerChannelDirections</u>
ps5000aSetTriggerChannelProperties

set up signal polarities for triggering set up trigger thresholds

ps5000aSetTriggerDelay set up post-trigger delay ps5000aSigGenArbitraryMinMaxValues get AWG parameters

ps5000aSigGenFrequencyToPhase ps5000aSigGenSoftwareControl ps5000aStop ps5000aStreamingReady convert frequency to phase count trigger the signal generator stop data capture indicate when streaming-mode data ready 26 API functions

11.1 ps5000aBlockReady (callback)

This <u>callback</u> function is part of your application. You register it with the PicoScope 5000A series driver using <u>ps5000aRunBlock</u>, and the driver calls it back when block-mode data is ready. You can then download the data using the <u>ps5000aGetValues</u> function.

Applicability	Block mode only
Arguments	handle, the handle of the device returning the samples.
	status, indicates whether an error occurred during collection of the data.
	* pParameter, a void pointer passed from ps5000aRunBlock . Your callback function can write to this location to send any data, such as a status flag, back to your application.
Returns	nothing

11.2 ps5000aChangePowerSource

```
PICO_STATUS ps5000aChangePowerSource
(
  int16_t handle,
  PICO_STATUS powerstate
)
```

This function selects the power supply mode. If USB power is required, you must explicitly allow it by calling this function. If the AC power adapter is connected or disconnected during use, you must also call this function. If you change power source to PICO_POWER_SUPPLY_NOT_CONNECTED and channels C/D are currently enabled, they will be switched off. If a trigger is set using channels C/D the trigger settings for those channels will also be removed.

Applicability	All modes. 4-Channel 5000 A and B Series oscilloscopes only
Arguments	handle, the handle of the device.
	powerstate, the required state of the unit. Either PICO POWER SUPPLY CONNECTED or
	PICO_POWER_SUPPLY_NOT_CONNECTED.
Returns	PICO_OK PICO_POWER_SUPPLY_REQUEST_INVALID PICO_INVALID_PARAMETER PICO_NOT_RESPONDING PICO_INVALID_HANDLE

28 API functions

11.3 ps5000aCloseUnit

```
PICO_STATUS ps5000aCloseUnit
(
  int16_t handle
)
```

This function shuts down a PicoScope 5000A oscilloscope.

Applicability	All modes
Arguments	handle, the handle, returned by ps5000aOpenUnit , of the scope
	device to be closed.
<u>Returns</u>	PICO_OK
	PICO_HANDLE_INVALID
	PICO_USER_CALLBACK
	PICO_DRIVER_FUNCTION

11.4 ps5000aCurrentPowerSource

```
PICO_STATUS ps5000aCurrentPowerSource
(
  int16_t handle
)
```

This function returns the current power state of the device.

Applicability	All modes. 4-Channel 5000 A and B Series oscilloscopes only
Arguments	handle, the handle of the device
Returns	PICO_INVALID_HANDLE - handle of the device is not recognised. PICO_POWER_SUPPLY_CONNECTED - if the device is powered by the AC adapter. PICO_POWER_SUPPLY_NOT_CONNECTED - if the device is powered by the USB cable.

30 API functions

11.5 ps5000aDataReady (callback)

This is a <u>callback</u> function that you write to collect data from the driver. You supply a pointer to the function when you call <u>ps5000aGetValuesAsync</u>, and the driver calls your function back when the data is ready.

Applicability	All modes
Arguments	handle, the handle of the device returning the samples.
	status, a PICO_STATUS code returned by the driver.
	noOfSamples, the number of samples collected.
	overflow, a set of flags that indicates whether an overvoltage has occurred and on which channels. It is a bit field with bit 0 representing Channel A.
	* pParameter, a void pointer passed from ps5000aGetValuesAsync. The callback function can write to this location to send any data, such as a status flag, back to the application. The data type is defined by the application programmer.
Returns	nothing

11.6 ps5000aEnumerateUnits

```
PICO_STATUS ps5000aEnumerateUnits
(
  int16_t     * count,
  int8_t     * serials,
  int16_t     * serialLth
)
```

This function counts the number of PicoScope 5000A units connected to the computer, and returns a list of serial numbers as a string.

Applicability	All modes
Arguments	* count, on exit, the number of PicoScope 5000A units found
	* serials, on exit, a list of serial numbers separated by commas and terminated by a final null. Example: AQ005/139,VDR61/356,ZOR14/107. Can be NULL on entry if serial numbers are not required.
	* serialLth, on entry, the length of the int8_t buffer pointed to by serials; on exit, the length of the string written to serials
Returns	PICO_OK PICO_BUSY PICO_NULL_PARAMETER PICO_FW_FAIL PICO_CONFIG_FAIL PICO_MEMORY_FAIL PICO_CONFIG_FAIL PICO_CONFIG_FAIL_AWG PICO_INITIALISE_FPGA

11.7 ps5000aFlashLed

```
PICO_STATUS ps5000aFlashLed
(
   int16_t handle,
   int16_t start
)
```

This function flashes the LED on the front of the scope without blocking the calling thread. Calls to ps5000aRunBlock cancel any flashing started by this function. It is not possible to set the LED to be constantly illuminated, as this state is used to indicate that the scope has not been initialized.

Applicability	All modes
Arguments	handle, the handle of the scope device
	start, the action required: -
	< 0 : flash the LED indefinitely.
	0 : stop the LED flashing.
	> 0 : flash the LED start times. If the LED is already flashing
	on entry to this function, the flash count will be reset to
	start.
Returns	PICO_OK
	PICO_HANDLE_INVALID
	PICO_BUSY
	PICO_DRIVER_FUNCTION
	PICO_NOT_RESPONDING

11.8 ps5000aGetAnalogueOffset

This function is used to get the maximum and minimum allowable analogue offset for a specific voltage range.

Applicability	Al models
Arguments	handle, the value returned from opening the device.
	range, the voltage range to be used when
	gathering the min and max information.
	coupling, the type of AC/DC coupling used.
	* maximumVoltage, a pointer to a float, an out parameter set to
	the maximum voltage allowed for the range, may be NULL.
	* minimumVoltage, a pointer to a float, an out parameter set to
	the minimum voltage allowed for the range, may be NULL.
	If both maximumVoltage and minimumVoltage are set to NULL the
	driver will return PICO_NULL_PARAMETER.
Returns	PICO_OK
	PICO_INVALID_HANDLE
	PICO_DRIVER_FUNCTION
	PICO_INVALID_VOLTAGE_RANGE
	PICO_NULL_PARAMETER

11.9 ps5000aGetChannelInformation

```
PICO_STATUS ps5000aGetChannelInformation (

int16_t handle,
    PS5000A_CHANNEL_INFO info,
    int32_t probe,
    int32_t * ranges,
    int32_t * length,
    int32_t channels
```

This function queries which ranges are available on a scope device.

Applicability	All modes	
Arguments	handle,	the handle of the required device.
	info,	the type of information required. The following value is currently supported: PS5000A_CI_RANGES
	probe,	not used, must be set to 0.
	* ranges,	an array that will be populated with available PS5000A_RANGE values for the given info. If NULL, length is set to the number of ranges available.
	* length,	on input: the length of the ranges array; on output: the number of elements written to ranges array.
	channels,	the channel for which the information is required.
<u>Returns</u>	PICO_NOT_F	ER_FUNCTION RESPONDING
	PICO_INVAL	_

$11.10 \quad ps 5000 a Get Device Resolution$

This function retrieves the resolution the specified device will run in.

Applicability	All modes
Arguments	handle, the handle of the required device
	* resolution, returns the resolution of the device, values are one of the PS5000A_DEVICE_RESOLUTION.
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO_NULL_PARAMETER

11.11 ps5000aGetMaxDownSampleRatio

This function returns the maximum downsampling ratio that can be used for a given number of samples in a given downsampling mode.

Applicability	All modes
Arguments	handle, the handle of the required device
	noOfUnaggregatedSamples, the number of unprocessed samples to be downsampled
	* maxDownSampleRatio: the maximum possible downsampling ratio output
	downSampleRatioMode: the downsampling mode. See ps5000aGetValues
	segmentIndex, the memory segment where the data is stored
Returns	PICO_OK PICO_INVALID_HANDLE PICO_NO_SAMPLES_AVAILABLE PICO_NULL_PARAMETER PICO_INVALID_PARAMETER PICO_SEGMENT_OUT_OF_RANGE PICO_TOO_MANY_SAMPLES

11.12 ps5000aGetMaxSegments

This function returns the maximum number of segments allowed for the opened device. Refer to ps5000aMemorySegments for specific figures.

Applicability	All modes
Arguments	handle, the value returned from opening the device.
	* maxsegments, (output) the maximum number of segments allowed.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO_NULL_PARAMETER

11.13 ps5000aGetNoOfCaptures

```
PICO_STATUS ps5000aGetNoOfCaptures
(
  int16_t handle,
  uint32_t * nCaptures
)
```

This function finds out how many captures are available in rapid block mode after ${\tt ps5000aRunBlock}$ has been called when either the collection completed or the collection of waveforms was interrupted by calling ${\tt ps5000aStop}$. The returned value (nCaptures) can then be used to iterate through the number of segments using ${\tt ps5000aGetValues}$, or in a single call to ${\tt ps5000aGetValuesBulk}$ where it is used to calculate the toSegmentIndex parameter.

Applicability	Rapid block mode
Arguments	handle: handle of the required device.
	* nCaptures, output: the number of available captures that has been collected from calling ps5000aRunBlock .
<u>Returns</u>	PICO_OK
	PICO_DRIVER_FUNCTION
	PICO_INVALID_HANDLE
	PICO_NOT_RESPONDING
	PICO_NO_SAMPLES_AVAILABLE
	PICO_NULL_PARAMETER
	PICO_INVALID_PARAMETER
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_TOO_MANY_SAMPLES

11.14 ps5000aGetNoOfProcessedCaptures

```
PICO_STATUS ps5000aGetNoOfProcessedCaptures
(
  int16_t    handle,
  uint32_t * nProcessedCaptures
)
```

This function finds out how many captures in rapid block mode have been processed after $\underline{ps5000aRunBlock}$ has been called when either the collection completed or the collection of waveforms was interrupted by calling $\underline{ps5000aStop}$. The returned value (nCaptures) can then be used to iterate through the number of segments using $\underline{ps5000aGetValues}$, or in a single call to $\underline{ps5000aGetValuesBulk}$ where it is used to calculate the toSegmentIndex parameter.

Applicability	Rapid block mode
Arguments	handle: handle of the required device.
	* nProcessedCaptures, output: the number of available captures that has been collected from calling ps5000aRunBlock.
Returns	PICO_OK PICO_DRIVER_FUNCTION PICO_INVALID_HANDLE PICO_NO_SAMPLES_AVAILABLE PICO_NULL_PARAMETER PICO_INVALID_PARAMETER
	PICO_SEGMENT_OUT_OF_RANGE PICO_TOO_MANY_SAMPLES

11.15 ps5000aGetStreamingLatestValues

This function instructs the driver to return the next block of values to your <u>ps5000aStreamingReady</u> callback function. You must have previously called <u>ps5000aRunStreaming</u> beforehand to set up <u>streaming</u>.

Applicability	Streaming mode only
Arguments	handle, the handle of the required device.
	lpPs5000AReady, a pointer to your <u>ps5000aStreamingReady</u> callback function.
	* pParameter, a void pointer that will be passed to the
	ps5000aStreamingReady callback function. The callback function may
	optionally use this pointer to return information to the application.
Returns	PICO_OK
	PICO_POWER_SUPPLY_CONNECTED
	PICO_POWER_SUPPLY_NOT_CONNECTED
	PICO_INVALID_HANDLE
	PICO_NO_SAMPLES_AVAILABLE
	PICO_INVALID_CALL
	PICO_BUSY
	PICO_NOT_RESPONDING
	PICO_DRIVER_FUNCTION

11.16 ps5000aGetTimebase

```
PICO_STATUS ps5000aGetTimebase
(
  int16_t    handle,
  uint32_t    timebase,
  int32_t    noSamples,
  int32_t    * timeIntervalNanoseconds,
  int32_t    * maxSamples,
  uint32_t    segmentIndex
)
```

This function calculates the sampling rate and maximum number of samples for a given <u>timebase</u> under the specified conditions. The result will depend on the number of channels enabled by the last call to <u>ps5000aSetChannel</u>.

This function is provided for use with programming languages that do not support the float data type. The value returned in the timeIntervalNanoseconds argument is restricted to integers. If your programming language supports the float type, then we recommend that you use ps5000aGetTimebase2 instead.

To use ps5000aGetTimebase or ps5000aGetTimebase2, first estimate the timebase number that you require using the information in the timebase guide. Next, call one of these functions with the timebase that you have just chosen and verify that the timeIntervalNanoseconds argument that the function returns is the value that you require. You may need to iterate this process until you obtain the time interval that you need.

Applicability	All modes
Arguments	handle, the handle of the required device.
	timebase, <u>see timebase guide</u>
	noSamples, the number of samples required.
	* timeIntervalNanoseconds, on exit, the time interval between readings at the selected timebase. Use NULL if not required.
	* maxSamples, on exit, the maximum number of samples available. The scope reserves some memory for internal overheads and this may vary depending on the number of segments, number of channels enabled, and the timebase chosen. Use NULL if not required.
	segmentIndex, the index of the memory segment to use.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_TOO_MANY_SAMPLES PICO_INVALID_CHANNEL PICO_INVALID_TIMEBASE PICO_INVALID_PARAMETER PICO_SEGMENT_OUT_OF_RANGE PICO_DRIVER_FUNCTION

11.17 ps5000aGetTimebase2

This function is an upgraded version of ps5000aGetTimebase, and returns the time interval as a float rather than a long. This allows it to return sub-nanosecond time intervals. See ps5000aGetTimebase for a full description.

Applicability	All modes
Arguments	* timeIntervalNanoseconds, a pointer to the time interval between readings at the selected timebase. If a null pointer is passed, nothing will be written here. All other arguments: see ps5000aGetTimebase.
	All other digunients. see <u>ps3000dGetTimebase</u> .
<u>Returns</u>	See <u>ps5000aGetTimebase</u> .

11.18 ps5000aGetTriggerTimeOffset

```
PICO_STATUS ps5000aGetTriggerTimeOffset (

int16_t handle,

uint32_t * timeUpper,

uint32_t * timeLower,

PS5000A_TIME_UNITS * timeUnits,

uint32_t segmentIndex
)
```

This function gets the time, as two 4-byte values, at which the trigger occurred. Call it after block-mode data has been captured or when data has been retrieved from a previous block-mode capture. A 64-bit version of this function, ps5000aGetTriggerTimeOffset64, is also available.

A month on hellitary	Displayers do servid block and do
Applicability	Block mode, rapid block mode
Arguments	handle, the handle of the required device * timeUpper, on exit, the upper 32 bits of the time at which the trigger point occurred * timeLower, on exit, the lower 32 bits of the time at which the trigger point occurred * timeUnits, returns the time units in which timeUpper and timeLower are measured. The allowable values are: -
	PS5000A_FS PS5000A_PS PS5000A_NS PS5000A_US PS5000A_MS PS5000A_S segmentIndex, the number of the memory segment for which the information is required.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_DEVICE_SAMPLING PICO_SEGMENT_OUT_OF_RANGE PICO_NOT_USED_IN_THIS_CAPTURE_MODE PICO_NOT_RESPONDING PICO_NULL_PARAMETER PICO_NO_SAMPLES_AVAILABLE PICO_DRIVER_FUNCTION

11.19 ps5000aGetTriggerTimeOffset64

This function gets the time, as a single 64-bit value, at which the trigger occurred. Call it after <u>block-mode</u> data has been captured or when data has been retrieved from a previous block-mode capture. A 32-bit version of this function, <u>ps5000aGetTriggerTimeOffset</u>, is also available.

Applicability	Block mode, rapid block mode
Arguments	handle, the handle of the required device
	* time, on exit, the time at which the trigger point occurred
	* timeUnits, on exit, the time units in which time is measured.
	The possible values are: -
	PS5000A_FS
	PS5000A_PS PS5000A_NS
	PS5000A_US
	PS5000A_MS
	<u>PS5000A_S</u>
	segmentIndex, the number of the memory segment for which the
	information is required
<u>Returns</u>	PICO_OK
	PICO_INVALID_HANDLE
	PICO_DEVICE_SAMPLING
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_NOT_USED_IN_THIS_CAPTURE_MODE
	PICO_NOT_RESPONDING
	PICO_NULL_PARAMETER
	PICO_NO_SAMPLES_AVAILABLE
	PICO_DRIVER_FUNCTION

11.20 ps5000aGetUnitInfo

This function retrieves information about the specified oscilloscope. If the device fails to open, or no device is opened only the driver version is available.

Applicability	All modes
Arguments	handle, the handle of the device from which information is required. If an invalid handle is passed, only the driver versions can be read.
	* string, on exit, the unit information string selected specified by the info argument. If string is NULL, only requiredSize is returned.
	stringLength, the maximum number of chars that may be written to string.
	* requiredSize, on exit, the required length of the string array.
	info, a number specifying what information is required. The
	possible values are listed in the table below.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_NULL_PARAMETER
	PICO_INVALID_INFO PICO_INFO_UNAVAILABLE PICO_DRIVER_FUNCTION

inf	ō	Example
0	PICO_DRIVER_VERSION	1,0,0,1
	Version number of PicoScope 5000A DLL	
1	PICO_USB_VERSION	2.0
	Type of USB connection to device: 1.1 or 2.0	
2	PICO_HARDWARE_VERSION	1
	Hardware version of device	
3	PICO_VARIANT_INFO	5444B
	Variant number of device	
4	PICO_BATCH_AND_SERIAL	KJL87/6
	Batch and serial number of device	
5	PICO_CAL_DATE	30Sep09
	Calibration date of device	
6	PICO_KERNEL_VERSION	1.0
	Version of kernel driver	
7	PICO_DIGITAL_HARDWARE_VERSION	1
	Hardware version of the digital section	
8	PICO_ANALOGUE_HARDWARE_VERSION	1
	Hardware version of the analogue section	

11.21 ps5000aGetValues

```
PICO_STATUS ps5000aGetValues
  int16_t
                          handle,
  uint32_t
                          startIndex,
  uint32_t
                        * noOfSamples,
  uint32_t
                          downSampleRatio,
  PS5000A_RATIO_MODE
                          downSampleRatioMode,
                          segmentIndex,
  uint32 t
                        * overflow
  int16_t
)
```

This function returns block-mode data from the oscilloscope's buffer memory, with or without <u>downsampling</u>, starting at the specified sample number. It is used to get the stored data after data collection has stopped.

Applicability	Block mode, rapid block mode
Arguments	handle, the handle of the required device.
	startIndex, a zero-based index that indicates the start point for data collection. It is measured in sample intervals from the start of the buffer.
	* noOfSamples, on entry, the number of samples required. On exit, the actual number retrieved. The number of samples retrieved will not be more than the number requested, and the data retrieved starts at startIndex.
	downSampleRatio, the <u>downsampling</u> factor that will be applied to the raw data.
	downSampleRatioMode, which downsampling mode to use. The available values are: - PS5000A_RATIO_MODE_NONE (downSampleRatio is ignored) PS5000A_RATIO_MODE_AGGREGATE PS5000A_RATIO_MODE_AVERAGE PS5000A_RATIO_MODE_DECIMATE
	AGGREGATE, AVERAGE, DECIMATE are single-bit constants that can be ORed to apply multiple downsampling modes to the same data.
	segmentIndex, the zero-based number of the memory segment where the data is stored.
	* overflow, on exit, a set of flags that indicate whether an overvoltage has occurred on any of the channels. It is a bit field with bit 0 denoting Channel A.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED

PICO_NO_SAMPLES_AVAILABLE PICO_DEVICE_SAMPLING PICO_NULL_PARAMETER PICO_SEGMENT_OUT_OF_RANGE PICO STARTINDEX INVALID PICO ETS NOT RUNNING PICO BUFFERS NOT SET PICO_INVALID_PARAMETER PICO_TOO_MANY_SAMPLES PICO_DATA_NOT_AVAILABLE PICO_STARTINDEX_INVALID PICO_INVALID_SAMPLERATIO PICO INVALID CALL PICO_NOT_RESPONDING PICO_MEMORY PICO_RATIO_MODE_NOT_SUPPORTED PICO DRIVER FUNCTION

11.21.1 Downsampling modes

Various methods of data reduction, or **downsampling**, are possible with the PicoScope 5000A Series oscilloscopes. The downsampling is done at high speed by dedicated hardware inside the scope, making your application faster and more responsive than if you had to do all the data processing in software.

You specify the downsampling mode when you call one of the data collection functions such as <u>ps5000aGetValues</u>. The following modes are available:

PS5000A_RATIO_MODE_NONE	No downsampling. Returns raw data values.
PS5000A_RATIO_MODE_AGGREGATE	Reduces every block of n values to just two values: a minimum and a maximum. The minimum and maximum values are returned in two separate buffers.
PS5000A_RATIO_MODE_AVERAGE	Reduces every block of n values to a single value representing the average (arithmetic mean) of all the values.
PS5000A_RATIO_MODE_DECIMATE	Reduces every block of n values to just the first value in the block, discarding all the other values.

11.22 ps5000aGetValuesAsync

```
PICO_STATUS ps5000aGetValuesAsync
  int16_t
                         handle,
  uint32_t
                         startIndex,
  uint32_t
                         noOfSamples,
  uint32_t
                         downSampleRatio,
  PS5000A_RATIO_MODE
                         downSampleRatioMode,
                         segmentIndex,
  uint32 t
                       * lpDataReady,
  void
  void
                       * pParameter
)
```

This function returns data either with or without <u>downsampling</u>, starting at the specified sample number. It is used to get the stored data from the driver after data collection has stopped. It returns the data using a <u>callback</u>.

Applicability	Streaming mode and block mode
Arguments	handle, the handle of the required device
	F000 C W/ I
	startIndex: see ps5000aGetValues
	noOfSamples: see <u>ps5000aGetValues</u>
	downSampleRatio: see ps5000aGetValues
	downSampleRatioMode: see ps5000aGetValues
	segmentIndex: see ps5000aGetValues
	* lpDataReady, a pointer to the user-supplied function that will
	be called when the data is ready. This will be a ps5000aDataReady
	function for block-mode data or a ps5000aStreamingReady function
	for streaming-mode data.
	* pParameter, a void pointer that will be passed to the callback
	function. The data type is determined by the application.
Returns	PICO_OK
	PICO_POWER_SUPPLY_CONNECTED
	PICO_POWER_SUPPLY_NOT_CONNECTED
	PICO_INVALID_HANDLE
	PICO_NO_SAMPLES_AVAILABLE
	PICO_DEVICE_SAMPLING
	PICO_NULL_PARAMETER
	PICO_STARTINDEX_INVALID
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_INVALID_PARAMETER
	PICO_DATA_NOT_AVAILABLE
	PICO_INVALID_SAMPLERATIO
	PICO_INVALID_CALL
	PICO_DRIVER_FUNCTION

11.23 ps5000aGetValuesBulk

```
PICO_STATUS ps5000aGetValuesBulk
  int16_t
                          handle,
  uint32_t
                        * noOfSamples,
  uint32_t
                          fromSegmentIndex,
  uint32_t
                          toSegmentIndex,
  uint32_t
                          downSampleRatio,
                          downSampleRatioMode,
  PS5000A_RATIO_MODE
                        * overflow
  int16_t
)
```

This function retrieves waveforms captured using <u>rapid block mode</u>. The waveforms must have been collected sequentially and in the same run.

Applicability	Rapid block mode
Arguments	handle, the handle of the device
	* noOfSamples, on entry, the number of samples required; on exit, the actual number retrieved. The number of samples retrieved will not be more than the number requested. The data retrieved always starts with the first sample captured.
	<pre>fromSegmentIndex, the first segment from which the waveform should be retrieved</pre>
	toSegmentIndex, the last segment from which the waveform should be retrieved
	downSampleRatio: see ps5000aGetValues downSampleRatioMode: see ps5000aGetValues
	* overflow, an array of integers equal to or larger than the number of waveforms to be retrieved. Each segment index has a corresponding entry in the overflow array, with overflow[0] containing the flags for the segment numbered fromSegmentIndex and the last element in the array containing the flags for the segment numbered toSegmentIndex. Each element in the array is a bit field as described under ps5000aGetValues.
Returns	PICO_OK PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_INVALID_HANDLE PICO_INVALID_PARAMETER PICO_INVALID_SAMPLERATIO PICO_ETS_NOT_RUNNING PICO_BUFFERS_NOT_SET PICO_TOO_MANY_SAMPLES PICO_SEGMENT_OUT_OF_RANGE PICO_NO_SAMPLES_AVAILABLE PICO_NOT_RESPONDING PICO_DRIVER_FUNCTION

11.24 ps5000aGetValuesOverlapped

```
PICO_STATUS ps5000aGetValuesOverlapped
  int16_t
                           handle,
  uint32_t
                           startIndex,
  uint32_t
                         * noOfSamples,
  uint32_t
                           downSampleRatio,
  PS5000A_RATIO_MODE
                           downSampleRatioMode,
                           segmentIndex,
  uint32_t
                         * overflow
  int16 t
)
```

This function allows you to make a deferred data-collection request, which will later be executed, and the arguments validated, when you call ps5000aRunBlock in block mode. The advantage of this function is that the driver makes contact with the scope only once, when you call ps5000aRunBlock, compared with the two contacts that occur when you use the conventional ps5000aRunBlock, ps5000aGetValues calling sequence. This slightly reduces the dead time between successive captures in block mode.

After calling <u>ps5000aRunBlock</u>, you can optionally use <u>ps5000aGetValues</u> to request further copies of the data. This might be required if you wish to display the data with different data reduction settings.

Applicability	Block mode
Arguments	handle, the handle of the device
	<pre>startIndex: see ps5000aGetValues * noOfSamples: see ps5000aGetValues downSampleRatio: see ps5000aGetValues downSampleRatioMode: see ps5000aGetValues segmentIndex: see ps5000aGetValues * overflow: see ps5000aGetValuesBulk</pre>
Returns	PICO_OK PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_INVALID_HANDLE PICO_INVALID_PARAMETER PICO_DRIVER_FUNCTION

11.25 ps5000aGetValuesOverlappedBulk

```
PICO_STATUS ps5000aGetValuesOverlappedBulk
  int16_t
                           handle,
  uint32_t
                           startIndex,
  uint32_t
                         * noOfSamples,
  uint32_t
                           downSampleRatio,
  PS5000A_RATIO_MODE
                           downSampleRatioMode,
  uint32_t
                           fromSegmentIndex,
  uint32 t
                           toSegmentIndex,
                         * overflow
  int16_t
)
```

This function allows you to make a deferred data-collection request, which will later be executed, and the arguments validated, when you call ps5000aRunBlock in rapid block mode. The advantage of this method is that the driver makes contact with the scope only once, when you call ps5000aRunBlock, compared with the two contacts that occur when you use the conventional ps5000aRunBlock, ps5000aGetValuesBulk calling sequence. This slightly reduces the dead time between successive captures in rapid block mode.

After calling <u>ps5000aRunBlock</u>, you can optionally use <u>ps5000aGetValues</u> to request further copies of the data. This might be required if you wish to display the data with different data reduction settings.

Applicability	Rapid block mode
Arguments	handle, the handle of the device
	<pre>startIndex: see ps5000aGetValues * noOfSamples: see ps5000aGetValues downSampleRatio: see ps5000aGetValues downSampleRatioMode: see ps5000aGetValues fromSegmentIndex: see ps5000aGetValuesBulk toSegmentIndex: see ps5000aGetValuesBulk * overflow, see ps5000aGetValuesBulk</pre>
<u>Returns</u>	PICO_OK PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_INVALID_HANDLE PICO_INVALID_PARAMETER PICO_DRIVER_FUNCTION

11.26 ps5000aGetValuesTriggerTimeOffsetBulk

This function retrieves the time offsets, as lower and upper 32-bit values, for waveforms obtained in <u>rapid block mode</u>.

This function is provided for use in programming environments that do not support 64-bit integers. If your programming environment supports this data type, it is easier to use <u>ps5000aGetValuesTriggerTimeOffsetBulk64</u>.

Applicability	Rapid block mode
Arguments	handle, the handle of the device
	* timesUpper, an array of integers. On exit, the most significant 32 bits of the time offset for each requested segment index. times[0] will hold the fromSegmentIndex time offset and the last times index will hold the toSegmentIndex time offset. The array must be long enough to hold the number of requested times.
	* timesLower, an array of integers. On exit, the least-significant 32 bits of the time offset for each requested segment index. times[0] will hold the fromSegmentIndex time offset and the last times index will hold the toSegmentIndex time offset. The array size must be long enough to hold the number of requested times.
	* timeUnits, an array of integers. The array must be long enough to hold the number of requested times. On exit, timeUnits[0] will contain the time unit for fromSegmentIndex and the last element will contain the time unit for toSegmentIndex. Refer to ps5000aGetTriggerTimeOffset for specific figures
	<pre>fromSegmentIndex, the first segment for which the time offset is required</pre>
	toSegmentIndex, the last segment for which the time offset is required. If toSegmentIndex is less than fromSegmentIndex then the driver will wrap around from the last segment to the first.
Returns	PICO_OK PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_INVALID_HANDLE PICO_NOT_USED_IN_THIS_CAPTURE_MODE PICO_NOT_RESPONDING PICO_NULL_PARAMETER PICO_DEVICE_SAMPLING PICO_SEGMENT_OUT_OF_RANGE PICO_NO_SAMPLES_AVAILABLE
	PICO_DRIVER_FUNCTION

11.27 ps5000aGetValuesTriggerTimeOffsetBulk64

```
PICO_STATUS ps5000aGetValuesTriggerTimeOffsetBulk64 (

int16_t handle,
   __int64 * times,
   PS5000A_TIME_UNITS * timeUnits,
   uint32_t fromSegmentIndex,
   uint32_t toSegmentIndex
)
```

This function retrieves the 64-bit time offsets for waveforms captured in rapid block mode.

A 32-bit version of this function, <u>ps5000aGetValuesTriggerTimeOffsetBulk</u>, is available for use with programming languages that do not support 64-bit integers.

Applicability	Rapid block mode
Arguments	handle, the handle of the device
	* times, an array of integers. On exit, this will hold the time offset for each requested segment index. times[0] will hold the time offset for fromSegmentIndex, and the last times index will hold the time offset for toSegmentIndex. The array must be long enough to hold the number of times requested.
	* timeUnits, an array of integers long enough to hold the number of requested times. timeUnits[0] will contain the time unit for fromSegmentIndex, and the last element will contain the toSegmentIndex. Refer to ps5000aGetTriggerTimeOffset64 for specific figures.
	<pre>fromSegmentIndex, the first segment for which the time offset is required. The results for this segment will be placed in times[0] and timeUnits[0].</pre>
	toSegmentIndex, the last segment for which the time offset is required. The results for this segment will be placed in the last elements of the times and timeUnits arrays. If toSegmentIndex is less than fromSegmentIndex then the driver will wrap around from the last segment to the first
Poturns	from the last segment to the first. PICO OK
<u>Returns</u>	PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_INVALID_HANDLE
	PICO_NOT_USED_IN_THIS_CAPTURE_MODE
	PICO_NOT_RESPONDING PICO NULL PARAMETER
	PICO_DEVICE_SAMPLING
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_NO_SAMPLES_AVAILABLE
	PICO_DRIVER_FUNCTION

11.28 ps5000alsReady

```
PICO_STATUS ps5000alsReady
(
  int16_t handle,
  int16_t * ready
)
```

This function may be used instead of a callback function to receive data from ${\tt ps5000aRunBlock}$. To use this method, pass a NULL pointer as the ${\tt lpReady}$ argument to ${\tt ps5000aRunBlock}$. You must then poll the driver to see if it has finished collecting the requested samples.

Applicability	Block mode
Arguments	handle, the handle of the required device
	* ready: output: indicates the state of the collection. If zero, the device is still collecting. If non-zero, the device has finished collecting and ps5000aGetValues can be used to retrieve the data.
<u>Returns</u>	PICO_OK
	PICO_INVALID_HANDLE
	PICO_DRIVER_FUNCTION
	PICO_NULL_PARAMETER
	PICO_NO_SAMPLES_AVAILABLE
	PICO_CANCELLED
	PICO_NOT_RESPONDING

11.29 ps5000alsTriggerOrPulseWidthQualifierEnabled

```
PICO_STATUS ps5000alsTriggerOrPulseWidthQualifierEnabled
(
  int16_t handle,
  int16_t * triggerEnabled,
  int16_t * pulseWidthQualifierEnabled
)
```

This function discovers whether a trigger, or pulse width triggering, is enabled.

Applicability	Call after setting up the trigger, and just before calling either ps5000aRunBlock or ps5000aRunStreaming.
Arguments	handle, the handle of the required device
	* triggerEnabled, on exit, indicates whether the trigger will successfully be set when ps5000aRunStreaming is called. A non-zero value indicates that the trigger is set, zero that the trigger is not set.
	* pulseWidthQualifierEnabled, on exit, indicates whether the pulse width qualifier will successfully be set when ps5000aRunBlock or ps5000aRunStreaming is called. A non-zero value indicates that the pulse width qualifier is set, zero that the pulse width qualifier is not set.
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_NULL_PARAMETER PICO_DRIVER_FUNCTION

11.30 ps5000aMaximumValue

```
PICO_STATUS ps5000aMaximumValue
(
  int16_t handle,
  int16_t * value
)
```

This function returns a status code and outputs the maximum ADC count value to a parameter. The output value depends on the currently selected resolution.

Applicability	All modes
Arguments	handle, the handle of the required device
	* value, pointer to an int16_t, (output) set to the maximum ADC value.
<u>Returns</u>	PICO_OK
	PICO_USER_CALLBACK
	PICO_INVALID_HANDLE
	PICO_TOO_MANY_SEGMENTS
	PICO_MEMORY
	PICO_DRIVER_FUNCTION

11.31 ps5000aMemorySegments

```
PICO_STATUS ps5000aMemorySegments
(
  int16_t handle,
  uint32_t nSegments,
  int32_t * nMaxSamples
)
```

This function sets the number of memory segments that the scope will use.

When the scope is <u>opened</u>, the number of segments defaults to 1, meaning that each capture fills the scope's available memory. This function allows you to divide the memory into a number of segments so that the scope can store several waveforms sequentially.

Applicability	All modes
Arguments	handle, the handle of the required device
	nSegments, the number of segments required, from:
	1 to 65,535: PicoScope 5242A/B, 5243A/B, 5442A/B, 5443A/B 1 to 125,000: PicoScope 5244A, 5444A 1 to 250,000: PicoScope 5244B, 5444B
	* nMaxSamples, on exit, the number of samples available in each segment. This is the total number over all channels, so if more than one channel is in use then the number of samples available to each channel is nMaxSamples divided by the number of channels.
Returns	PICO_OK PICO_USER_CALLBACK PICO_INVALID_HANDLE PICO_TOO_MANY_SEGMENTS PICO_MEMORY

11.32 ps5000aMinimumValue

```
PICO_STATUS ps5000aMinimumValue
(
  int16_t handle,
  int16_t * value
)
```

This function returns a status code and outputs the minimum ADC count value to a parameter. The output value depends on the currently selected resolution.

Applicability	All modes
Arguments	handle, the handle of the required device
	* value, pointer to an int16_t, (output) set to the minimum ADC value.
<u>Returns</u>	PICO_OK
	PICO_USER_CALLBACK
	PICO_INVALID_HANDLE
	PICO_TOO_MANY_SEGMENTS
	PICO_MEMORY
	PICO_DRIVER_FUNCTION

11.33 ps5000aNoOfStreamingValues

```
PICO_STATUS ps5000aNoOfStreamingValues
(
  int16_t handle,
  uint32_t * noOfValues
)
```

This function returns the number of samples available after data collection in streaming mode. Call it after calling ps5000aStop.

Applicability	Streaming mode
Arguments	handle, the handle of the required device
	* noOfValues, on exit, the number of samples
<u>Returns</u>	PICO_OK
	PICO_INVALID_HANDLE
	PICO_NULL_PARAMETER
	PICO_NO_SAMPLES_AVAILABLE
	PICO_NOT_USED
	PICO_BUSY
	PICO_DRIVER_FUNCTION

11.34 ps5000aOpenUnit

This function opens a PicoScope 5000A or 5000B Series scope attached to the computer. The maximum number of units that can be opened depends on the operating system, the kernel driver and the computer. If ps5000aOpenUnit is called without the power supply connected, the driver returns PICO_POWER_SUPPLY_NOT_CONNECTED.

Applicability	All modes
Arguments	<pre>* handle, on exit, the result of the attempt to open a scope: -1 : if the scope fails to open 0 : if no scope is found > 0 : a number that uniquely identifies the scope If a valid handle is returned, it must be used in all subsequent calls to API functions to identify this scope. * serial, on entry, a null-terminated string containing the serial number of the scope to be opened. If serial is NULL then the function opens the first scope found; otherwise, it tries to open the scope that matches the string. resolution, determines the resolution of the device when opened, the available values are one of the PS5000A_DEVICE_RESOLUTION. If resolution is out of range the device will return PICO_INVALID_DEVICE_RESOLUTION.</pre>
Returns	PICO_OK PICO_OS_NOT_SUPPORTED PICO_INVALID_DEVICE_RESOLUTION. PICO_OPEN_OPERATION_IN_PROGRESS PICO_EEPROM_CORRUPT PICO_KERNEL_DRIVER_TOO_OLD PICO_FPGA_FAIL PICO_MEMORY_CLOCK_FREQUENCY PICO_FW_FAIL PICO_MAX_UNITS_OPENED PICO_NOT_FOUND (if the specified unit was not found) PICO_NOT_RESPONDING PICO_MEMORY_FAIL PICO_ANALOG_BOARD PICO_CONFIG_FAIL_AWG PICO_INITIALISE_FPGA PICO_POWER_SUPPLY_NOT_CONNECTED

11.35 ps5000aOpenUnitAsync

This function opens a scope without blocking the calling thread. You can find out when it has finished by periodically calling ps5000aOpenUnitProgress until that function returns a non-zero value.

Applicability	All modes
Arguments	<pre>* status, a status code: 0 if the open operation was disallowed because another open operation is in progress 1 if the open operation was successfully started * serial: see ps5000aOpenUnit</pre>
	resolution, determines the resolution of the device when opened, the available values are one of the PS5000A_DEVICE_RESOLUTION . If resolution is out of range the device will return PICO_INVALID_DEVICE_RESOLUTION .
Returns	PICO_OK PICO_INVALID_DEVICE_RESOLUTION PICO_OPEN_OPERATION_IN_PROGRESS PICO_OPERATION_FAILED

11.36 ps5000aOpenUnitProgress

```
PICO_STATUS ps5000aOpenUnitProgress
(
  int16_t * handle,
  int16_t * progressPercent,
  int16_t * complete
)
```

This function checks on the progress of a request made to <u>ps5000aOpenUnitAsync</u> to open a scope.

Applicability	Use after ps5000aOpenUnitAsync
Arguments	* handle: see ps5000aOpenUnit . This handle is valid only if the function returns PICO_OK.
	* progressPercent, on exit, the percentage progress towards opening the scope. 100% implies that the open operation is complete.
	* complete, set to 1 when the open operation has finished
Returns	PICO_OK PICO_NULL_PARAMETER PICO_OPERATION_FAILED

11.37 ps5000aPingUnit

```
PICO_STATUS ps5000aPingUnit
(
  int16_t handle
)
```

This function can be used to check that the already opened device is still connected to the USB port and communication is successful.

Applicability	All modes
Arguments	handle, the handle of the required device
Returns	PICO_OK PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED PICO_BUSY PICO_NOT_RESPONDING

11.38 ps5000aRunBlock

```
PICO_STATUS ps5000aRunBlock
  int16_t
                      handle,
  int32_t
                      noOfPreTriggerSamples,
  int32_t
                      noOfPostTriggerSamples,
  uint32_t
                      timebase,
                    * timeIndisposedMs,
  int32_t
  uint32 t
                      segmentIndex,
  ps5000aBlockReady
                      lpReady,
                     * pParameter
  void
)
```

This function starts collecting data in <u>block mode</u>. For a step-by-step guide to this process, see <u>Using block mode</u>.

The number of samples is determined by noOfPreTriggerSamples and noOfPostTriggerSamples (see below for details). The total number of samples must not be more than the size of the segment referred to by segment Index.

Applicability	Block mode, rapid block mode
Arguments	handle, the handle of the required device.
	noOfPreTriggerSamples, the number of samples to return before the trigger event. If no trigger has been set then this argument is ignored and noOfPostTriggerSamples specifies the maximum number of samples to collect.
	noOfPostTriggerSamples, the number of samples to be taken after a trigger event. If no trigger event has been set then this specifies the maximum number of samples to be taken. If a trigger condition has been set, this specifies the number of samples to be taken after a trigger has fired, and the number of samples to be collected is then: -
	noOfPreTriggerSamples + noOfPostTriggerSamples
	timebase, a number in the range 0 to 2^{32} -1. See the guide to calculating timebase values.
	* timeIndisposedMs, on exit, the time, in milliseconds, that the scope will spend collecting samples. This does not include any auto trigger timeout. If this pointer is null, nothing will be written here.
	segmentIndex, zero-based, specifies which memory segment to use.
	lpReady, a pointer to the ps5000aBlockReady callback function that the driver will call when the data has been collected. To use the ps5000aIsReady polling method instead of a callback function, set this pointer to NULL.
	* pParameter, a void pointer that is passed to the <pre>ps5000aBlockReady</pre> callback function. The callback can use this pointer to return arbitrary data to the application.

Returns	PICO_OK
	PICO_POWER_SUPPLY_CONNECTED
	PICO_POWER_SUPPLY_NOT_CONNECTED
	PICO_BUFFERS_NOT_SET (in Overlapped mode)
	PICO_INVALID_HANDLE
	PICO_USER_CALLBACK
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_INVALID_CHANNEL
	PICO_INVALID_TRIGGER_CHANNEL
	PICO_INVALID_CONDITION_CHANNEL
	PICO_TOO_MANY_SAMPLES
	PICO_INVALID_TIMEBASE
	PICO_NOT_RESPONDING
	PICO_CONFIG_FAIL
	PICO_INVALID_PARAMETER
	PICO_NOT_RESPONDING
	PICO_TRIGGER_ERROR
	PICO_DRIVER_FUNCTION
	PICO_FW_FAIL
	PICO_NOT_ENOUGH_SEGMENTS (in Bulk mode)
	PICO_PULSE_WIDTH_QUALIFIER
	PICO_SEGMENT_OUT_OF_RANGE (in Overlapped mode)
	PICO_STARTINDEX_INVALID (in Overlapped mode)
	PICO_INVALID_SAMPLERATIO (in Overlapped mode)
	PICO_CONFIG_FAIL

11.39 ps5000aRunStreaming

```
PICO_STATUS ps5000aRunStreaming
  int16_t
                           handle,
  uint32_t
                         * sampleInterval,
  PS5000A_TIME_UNITS
                           sampleIntervalTimeUnits,
  uint32_t
                           maxPreTriggerSamples,
                           maxPostTriggerSamples,
  uint32_t
  int16 t
                           autoStop,
  uint32 t
                           downSampleRatio,
                           downSampleRatioMode,
  PS5000A_RATIO_MODE
                           overviewBufferSize
 uint32_t
)
```

This function tells the oscilloscope to start collecting data in <u>streaming mode</u>. When data has been collected from the device it is <u>downsampled</u> if necessary and then delivered to the application. Call <u>ps5000aGetStreamingLatestValues</u> to retrieve the data. See <u>Using streaming mode</u> for a step-by-step guide to this process.

When a trigger is set, the total number of samples stored in the driver is the sum of maxPreTriggerSamples and maxPostTriggerSamples. If autoStop is false then this will become the maximum number of samples without downsampling.

Applicability	Streaming mode
Arguments	handle, the handle of the required device.
	* sampleInterval, on entry, the requested time interval between samples; on exit, the actual time interval used.
	sampleIntervalTimeUnits, the unit of time used for sampleInterval. Use one of these values: PS5000A_FS PS5000A_NS PS5000A_US PS5000A_MS PS5000A_S
	maxPreTriggerSamples, the maximum number of raw samples before a trigger event for each enabled channel. If no trigger condition is set this argument is ignored.
	maxPostTriggerSamples, the maximum number of raw samples after a trigger event for each enabled channel. If no trigger condition is set, this argument states the maximum number of samples to be stored.
	autoStop, a flag that specifies if the streaming should stop when all of maxSamples have been captured.
	downSampleRatio: see ps5000aGetValues downSampleRatioMode: see ps5000aGetValues
	overviewBufferSize, the size of the overview buffers. These are temporary buffers used for storing the data before returning it to the application. The size is the same as the bufferLth value passed to ps5000aSetDataBuffer.
Returns	PICO_OK PICO_INVALID_HANDLE

PICO_ETS_MODE_SET

PICO_USER_CALLBACK

PICO_NULL_PARAMETER

PICO_INVALID_PARAMETER

PICO_STREAMING_FAILED

PICO_NOT_RESPONDING

PICO_POWER_SUPPLY_CONNECTED

PICO_POWER_SUPPLY_NOT_CONNECTED

PICO_TRIGGER_ERROR

PICO_INVALID_SAMPLE_INTERVAL

PICO_INVALID_BUFFER

PICO_DRIVER_FUNCTION

PICO_FW_FAIL

PICO_MEMORY

11.40 ps5000aSetBandwidthFilter

```
PICO_STATUS ps5000aSetBandwidthFilter (
   int16_t handle,
   PS5000A_CHANNEL channel,
   PS5000A_BANDWIDTH_LIMITER bandwidth
```

This function controls the hardware bandwidth limiter.

Applicability	All modes. All models.
Arguments	handle, the handle of the required device
	channel, the channel to be configured. The values are: PS5000A_CHANNEL_A: Channel A input PS5000A_CHANNEL_B: Channel B input PS5000A_CHANNEL_C: Channel C input PS5000A_CHANNEL_D: Channel D input bandwidth, the bandwidth is either PS5000A_BW_FULL or PS5000A_BW_20MHZ
Returns	PICO OK
Returns	PICO_INVALID_HANDLE PICO_INVALID_CHANNEL PICO_INVALID_BANDWIDTH

11.41 ps5000aSetChannel

```
PICO_STATUS ps5000aSetChannel (

int16_t handle,
    PS5000A_CHANNEL channel,
    int16_t enabled,
    PS5000A_COUPLING type,
    PS5000A_RANGE range,
    float analogueOffset
)
```

This function specifies whether an input channel is to be enabled, its input coupling type, voltage range, analog offset and bandwidth limit.

Applicability	All modes
Arguments	handle, the handle of the required device
	channel, the channel to be configured. The values are:
	PS5000A_CHANNEL_A: Channel A input
	PS5000A_CHANNEL_B: Channel B input
	PS5000A_CHANNEL_C: Channel C input
	PS5000A_CHANNEL_D: Channel D input
	enabled, whether or not to enable the channel. The values are: TRUE: enable FALSE: do not enable
	type, the impedance and coupling type. The values are: PS5000A_AC: 1 megohm impedance, AC coupling. The channel accepts input frequencies from about 1 hertz up to its maximum - 3 dB analog bandwidth.
	PS5000A_DC: 1 megohm impedance, DC coupling. The scope accepts all input frequencies from zero (DC) up to its maximum -3 dB analog bandwidth.
	range, the input voltage range:
	PS5000A_10MV: ±10 mV
	PS5000A_20MV: ±20 mV
	PS5000A_50MV: ±50 mV
	PS5000A_100MV: ±100 mV PS5000A_200MV: ±200 mV
	PS5000A_500MV: ±500 mV
	PS5000A 1V: ±1 V
	PS5000A_2V: ±2 V
	PS5000A_5V: ±5 V
	PS5000A_10V: ±10 V
	<u>PS5000A_20V</u> : ±20 V
	analogueOffset, a voltage to add to the input channel before digitization. The allowable range of offsets depends on the input
	range selected for the channel, as obtained from
	ps5000aGetAnalogueOffset.

Returns	PICO_OK
	PICO_USER_CALLBACK
	PICO_INVALID_HANDLE
	PICO_INVALID_CHANNEL
	PICO_INVALID_VOLTAGE_RANGE
	PICO_INVALID_COUPLING
	PICO INVALID ANALOGUE OFFSET
	PICO_DRIVER_FUNCTION

11.42 ps5000aSetDataBuffer

```
PICO_STATUS ps5000aSetDataBuffer (

int16_t handle,
    PS5000A_CHANNEL channel,
    int16_t * buffer,
    int32_t bufferLth,
    uint32_t segmentIndex,
    PS5000A_RATIO_MODE mode
)
```

This function tells the driver where to store the data, either unprocessed or downsampled, that will be returned after the next call to one of the GetValues functions. The function allows you to specify only a single buffer, so for aggregation mode, which requires two buffers, you need to call ps5000aSetDataBuffers instead.

You must allocate memory for the buffer before calling this function.

Applicability	Block, rapid block and streaming modes. All downsampling modes
Аррисавину	except aggregation.
Arguments	handle, the handle of the required device
	channel, the channel you want to use with the buffer. Use one of these values:
	PS5000A_CHANNEL_A
	PS5000A_CHANNEL_B
	PS5000A_CHANNEL_C
	PS5000A_CHANNEL_D
	* buffer, the location of the buffer
	bufferLth, the size of the buffer array
	segmentIndex, the number of the memory segment to be used
	mode, the <u>downsampling</u> mode. See <u>ps5000aGetValues</u> for the available modes, but note that a single call to <u>ps5000aSetDataBuffer</u> can only associate one buffer with one downsampling mode. If you intend to call <u>ps5000aGetValues</u> with more than one downsampling
	mode activated, then you must call <u>ps5000aSetDataBuffer</u> several times to associate a separate buffer with each downsampling mode.
Returns	PICO_OK
	PICO_INVALID_HANDLE
	PICO_INVALID_CHANNEL
	PICO_RATIO_MODE_NOT_SUPPORTED
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_DRIVER_FUNCTION
	PICO_INVALID_PARAMETER

11.43 ps5000aSetDataBuffers

```
PICO_STATUS ps5000aSetDataBuffers
                            handle,
  int16_t
  PS5000A_CHANNEL
                            channel,
  int16_t
                          * bufferMax,
  int16_t
                          * bufferMin,
  int32_t
                            bufferLth,
  uint32 t
                            segmentIndex,
  PS5000A_RATIO_MODE
                            mode
)
```

This function tells the driver the location of one or two buffers for receiving data. You need to allocate memory for the buffers before calling this function. If you do not need two buffers, because you are not using aggregate mode, then you can optionally use ps5000aSetDataBuffer instead.

Applicability	Plack and streaming modes with aggregation
Applicability	Block and streaming modes with aggregation.
Arguments	handle, the handle of the required device.
	channel, the channel for which you want to set the buffers. Use one of these constants:
	PS5000A_CHANNEL_A
	PS5000A CHANNEL B
	PS5000A CHANNEL C
	PS5000A_CHANNEL_D
	* bufferMax, a buffer to receive the maximum data values in aggregation mode, or the non-aggregated values otherwise.
	* bufferMin, a buffer to receive the minimum aggregated data values. Not used in other downsampling modes.
	bufferLth, the size of the bufferMax and bufferMin arrays.
	segmentIndex, the number of the memory segment to be used
	mode: see ps5000aGetValues
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE
	PICO_INVALID_CHANNEL
	PICO_RATIO_MODE_NOT_SUPPORTED
	PICO_SEGMENT_OUT_OF_RANGE
	PICO_DRIVER_FUNCTION
	PICO_INVALID_PARAMETER

11.44 ps5000aSetDeviceResolution

This function sets the new resolution. When using 12 bits or more the memory is halved. When using 15-bit resolution only 2 channels can be enabled to capture data, and when using 16-bit resolution only one channel is available. If resolution is changed, any data captured that has not been saved will be lost. If ps5000aSetChannel is not called, ps5000aRunBlock and ps5000aRunStreaming may fail.

Applicability	All modes
Arguments	* handle, on exit, the result of the attempt to open a scope: -1 : if the scope fails to open 0 : if no scope is found > 0 : a number that uniquely identifies the scope If a valid handle is returned, it must be used in all subsequent calls to API functions to identify this scope. resolution, determines the resolution of the device when opened, the available values are one of the PS5000A_DEVICE_RESOLUTION. If resolution is out of range the device will return PICO_INVALID_DEVICE_RESOLUTION.
Returns	PICO_OK PICO_INVALID_DEVICE_RESOLUTION PICO_OS_NOT_SUPPORTED PICO_OPEN_OPERATION_IN_PROGRESS PICO_EEPROM_CORRUPT PICO_KERNEL_DRIVER_TOO_OLD PICO_FPGA_FAIL PICO_MEMORY_CLOCK_FREQUENCY PICO_FW_FAIL PICO_MAX_UNITS_OPENED PICO_NOT_FOUND (if the specified unit was not found) PICO_NOT_RESPONDING PICO_MEMORY_FAIL PICO_ANALOG_BOARD PICO_CONFIG_FAIL_AWG PICO_INITIALISE_FPGA PICO_POWER_SUPPLY_NOT_CONNECTED

11.45 ps5000aSetEts

```
PICO_STATUS ps5000aSetEts
(
int16_t handle,
    PS5000A_ETS_MODE mode,
    int16_t etsCycles,
    int16_t etsInterleave,
    int32_t * sampleTimePicoseconds
)
```

This function is used to enable or disable $\underline{\sf ETS}$ (equivalent-time sampling) and to set the ETS parameters. See $\underline{\sf ETS}$ overview for an explanation of ETS mode.

Applicability	Block mode
Arguments	handle, the handle of the required device
	mode, the ETS mode. Use one of these values: PS5000A_ETS_OFF: disables ETS PS5000A_ETS_FAST: enables ETS and provides etsCycles of data, which may contain data from previously returned cycles PS5000A_ETS_SLOW: enables ETS and provides fresh data every etsCycles. This mode takes longer to provide each data set, but the data sets are more stable and are guaranteed to contain only new data.
	etsCycles, the number of cycles to store: the computer can then select etsInterleave cycles to give the most uniform spread of samples. Range: between two and five times the value of etsInterleave, and not more than either: PS5242A_MAX_ETS_CYCLES PS5243A_MAX_ETS_CYCLES PS5244A_MAX_ETS_CYCLES
	etsInterleave, the number of waveforms to combine into a single ETS capture. Maximum value is either: PS5242A_MAX_INTERLEAVE PS5243A_MAX_INTERLEAVE PS5244A_MAX_INTERLEAVE
	* sampleTimePicoseconds, on exit, the effective sampling interval of the ETS data. For example, if the captured sample time is 4 ns and etsInterleave is 10, then the effective sample time in ETS mode is 400 ps.
<u>Returns</u>	PICO_OK PICO_USER_CALLBACK PICO_INVALID_HANDLE PICO_INVALID_PARAMETER PICO_DRIVER_FUNCTION

11.46 ps5000aSetEtsTimeBuffer

```
PICO_STATUS ps5000aSetEtsTimeBuffer
(
  int16_t handle,
  __int64 * buffer,
  int32_t bufferLth
)
```

This function tells the driver where to find your application's ETS time buffers. These buffers contain the 64-bit timing information for each ETS sample after you run a block-mode ETS capture.

Applicability	ETS mode only.
	If your programming language does not support 64-bit data, use the 32-bit version <u>ps5000aSetEtsTimeBuffers</u> instead.
Arguments	handle, the handle of the required device
	* buffer, an array of 64-bit words, each representing the time in picoseconds at which the sample was captured bufferLth, the size of the buffer array
Returns	PICO_OK PICO_INVALID_HANDLE PICO_NULL_PARAMETER PICO_DRIVER_FUNCTION

11.47 ps5000aSetEtsTimeBuffers

This function tells the driver where to find your application's ETS time buffers. These buffers contain the timing information for each ETS sample after you run a <u>block-mode</u> ETS capture. There are two buffers containing the upper and lower 32-bit parts of the timing information, to allow programming languages that do not support 64-bit data to retrieve the timings.

Applicability	ETS mode only.
	If your programming language supports 64-bit data then you can use ps5000aSetEtsTimeBuffer instead.
Arguments	handle, the handle of the required device
	* timeUpper, an array of 32-bit words, each representing the upper 32 bits of the time in picoseconds at which the sample was captured
	* timeLower, an array of 32-bit words, each representing the lower 32 bits of the time in picoseconds at which the sample was captured
	bufferLth, the size of the timeUpper and timeLower arrays
<u>Returns</u>	PICO_OK
	PICO_INVALID_HANDLE
	PICO_NULL_PARAMETER
	PICO_DRIVER_FUNCTION

11.48 ps5000aSetNoOfCaptures

```
PICO_STATUS ps5000aSetNoOfCaptures
(
  int16_t handle,
  uint32_t nCaptures
)
```

This function sets the number of captures to be collected in one run of <u>rapid block</u> <u>mode</u>. If you do not call this function before a run, the driver will capture only one waveform. Once a value has been set, the value remains constant unless changed.

Applicability	Rapid block mode
Arguments	handle, the handle of the device
	nCaptures, the number of waveforms to capture in one run
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_INVALID_PARAMETER PICO_DRIVER_FUNCTION

11.49 ps5000aSetPulseWidthQualifier

```
PICO_STATUS ps5000aSetPulseWidthQualifier
  int16_t
                                 handle,
  PS5000A_PWQ_CONDITIONS
                               * conditions,
  int16_t
                                 nConditions,
  PS5000A_THRESHOLD_DIRECTION
                                 direction,
  uint32_t
                                 lower,
  uint32 t
                                 upper,
  PS5000A_PULSE_WIDTH_TYPE
                                 type
)
```

This function sets up pulse-width qualification, which can be used on its own for pulse-width triggering or combined with window triggering to produce more complex triggers. The pulse-width qualifier is set by defining one or more structures that are then ORed together. Each structure is itself the AND of the states of one or more of the inputs. This AND-OR logic allows you to create any possible Boolean function of the scope's inputs.

Applicability	All modes
Applicability Arguments	All modes handle, the handle of the required device * conditions, an array of PS5000A_PWQ_CONDITIONS structures specifying the conditions that should be applied to each channel. In the simplest case, the array consists of a single element. When there are several elements, the overall trigger condition is the logical OR of all the elements. If conditions is NULL then the pulse-width qualifier is not used.
	nConditions, the number of elements in the conditions array. If nConditions is zero then the pulse-width qualifier is not used. Range: 0 to PS5000A_MAX_PULSE_WIDTH_QUALIFIER_COUNT . direction, the direction of the signal required for the pulse width trigger to fire. See PS5000A_THRESHOLD_DIRECTION constants for the list of possible values. Each channel of the oscilloscope (except the EXT input) has two thresholds for each direction—for example, PS5000A_RISING and PS5000A_RISING LOWER—so that one can be used for the pulse-width qualifier and the other for the level trigger. The driver will not let you use the same threshold for both triggers; so, for example, you cannot use PS5000A_RISING as the direction argument for both ps5000aSetPulseWidthQualifier at the same time. There is no such restriction when using window triggers.
	lower, the lower limit of the pulse-width counter with relation to number of samples captured on the device. upper, the upper limit of the pulse-width counter with relation to number of samples captured on the device. This parameter is used only when the type is set to PS5000A_PW_TYPE_OUT_OF_RANGE .

Arguments	type, the pulse-width type, one of these constants: PS5000A_PW_TYPE_NONE: do not use the pulse width qualifier PS5000A_PW_TYPE_LESS_THAN: pulse width less than lower PS5000A_PW_TYPE_GREATER_THAN: pulse width greater than lower PS5000A_PW_TYPE_IN_RANGE: pulse width between lower and upper PS5000A_PW_TYPE_OUT_OF_RANGE: pulse width not between lower and upper
Returns	PICO_OK PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_CONDITIONS PICO_PULSE_WIDTH_QUALIFIER PICO_DRIVER_FUNCTION

11.49.1 ps5000a_PWQ_CONDITIONS structure

A structure of this type is passed to <u>ps5000aSetPulseWidthQualifier</u> in the conditions argument to specify the trigger conditions. It is defined as follows:

```
typedef struct tPS5000APwqConditions
{
   PS5000A_TRIGGER_STATE channelA;
   PS5000A_TRIGGER_STATE channelB;
   PS5000A_TRIGGER_STATE channelC;
   PS5000A_TRIGGER_STATE channelD;
   PS5000A_TRIGGER_STATE external;
   PS5000A_TRIGGER_STATE aux;
} PS5000A_PWO_CONDITIONS
```

Each structure is the logical AND of the states of the scope's inputs. The ps5000aSetPulseWidthQualifier function can OR together a number of these structures to produce the final pulse width qualifier, which can therefore be any possible Boolean function of the scope's inputs.

The structure is byte-aligned. In C++, for example, you should specify this using the $\#pragma\ pack()$ instruction.

Applicability	All models
Elements	channelA, channelB, channelC*, channelD*, external: the type of condition that should be applied to each channel. Use these constants: -
	<pre>PS5000A_CONDITION_DONT_CARE are ignored. aux: not used</pre>

^{*}Note: applicable to 4-channel analog devices only.

11.50 ps5000aSetSigGenArbitrary

```
PICO STATUS ps5000aSetSigGenArbitrary
  int16_t
                                   handle,
  int32_t
                                   offsetVoltage,
  uint32_t
                                   pkToPk,
  uint32_t
                                   startDeltaPhase,
  uint32_t
                                   stopDeltaPhase,
  uint32 t
                                   deltaPhaseIncrement,
  uint32 t
                                   dwellCount,
  int16 t
                                 * arbitraryWaveform,
  int32_t
                                   arbitraryWaveformSize,
  PS5000A_SWEEP_TYPE
                                   sweepType,
  PS5000A EXTRA OPERATIONS
                                   operation,
  PS5000A_INDEX_MODE
                                   indexMode,
  uint32_t
                                  shots,
  uint32_t
                                   sweeps,
  PS5000A_SIGGEN_TRIG_TYPE
                                  triggerType,
  PS5000A_SIGGEN_TRIG_SOURCE
                                  triggerSource,
                                   extInThreshold
  int16 t
```

This function programs the signal generator to produce an arbitrary waveform.

The arbitrary waveform generator uses direct digital synthesis (DDS). It maintains a 32-bit phase accumulator that indicates the present location in the waveform. The top bits of the phase accumulator are used as an index into a buffer containing the arbitrary waveform. The remaining bits act as the fractional part of the index, enabling high-resolution control of output frequency and allowing the generation of lower frequencies.

The generator steps through the waveform by adding a *deltaPhase* value between 1 and *phaseAccumulatorSize-1* to the phase accumulator every *dacPeriod* (1/ *dacFrequency*). If *deltaPhase* is constant, the generator produces a waveform at a constant frequency that can be calculated as follows:

```
outputFrequency = dacFrequency \times \left(\frac{deltaPhase}{phaseAccumulatorSize}\right) \times \left(\frac{awgBufferSize}{arbitraryWaveformSize}\right)
```

where:

awgBufferSize = maximum AWG buffer size (see table below)
arbitraryWaveformSize = length in samples of the user-defined waveform

You can call <u>ps5000aSigGenFrequencyToPhase()</u> to calculate the value for *deltaPhase* for the desired frequency.

Parameter	PicoScope 5242B PicoScope 5442B	PicoScope 5243B PicoScope 5443B	PicoScope 5244B PicoScope 5444B
dacFrequency		200 MHz	
dacPeriod (= 1/dacFrequency)	5 ns		
phaseAccumulatorSize	4 294 967 296 (2 ³²)		
awgBufferSize	16 384 (2 ¹⁴)	32 768 (2 ¹⁵)	49 152 (3 × 2 ¹⁴)

It is also possible to sweep the frequency by continually modifying the *deltaPhase*. This is done by setting up a *deltaPhaseIncrement* that the oscilloscope adds to the *deltaPhase* at specified intervals.


Applicability	All modes. B models only.		
Arguments	handle, the handle of the required device		
	offsetVoltage, the voltage offset, in microvolts, to be applied to the waveform.		
	<pre>pkToPk, the peak-to-peak voltage, in microvolts, of the waveform signal. Note that if the signal voltages defined by the combination of offsetVoltage and pkToPk extend outside the voltage range of the signal generator, the output waveform will be clipped.</pre>		
	startDeltaPhase, the initial value added to the phase accumulator as the generator begins to step through the waveform buffer.		
	stopDeltaPhase, the final value added to the phase accumulator before the generator restarts or reverses the sweep.		
	deltaPhaseIncrement, the amount added to the delta phase value every time the dwellCount period expires. This determines the amount by which the generator sweeps the output frequency in each dwell period.		
	dwellCount, the time, in 50 ns steps, between successive additions of deltaPhaseIncrement to the delta phase accumulator. This determines the rate at which the generator sweeps the output frequency. Minimum value: PS5000A_MIN_DWELL_COUNT		
	* arbitraryWaveform, a buffer that holds the waveform pattern as a set of samples equally spaced in time. If pkToPk is set to its maximum (4 V) and offsetVoltage is set to 0, then a sample of -32768 corresponds to -2 V, and +32767 to +2 V.		
	arbitraryWaveformSize, the size of the arbitrary waveform buffer, in samples, from MIN_SIG_GEN_BUFFER_SIZE to MAX_SIG_GEN_BUFFER_SIZE or PS5444B MAX SIG GEN BUFFER SIZE.		
	sweepType, determines whether the startDeltaPhase is swept up to the stopDeltaPhase, or down to it, or repeatedly swept up and down. Use one of these values: - PS5000A_UP PS5000A_DOWN PS5000A_UPDOWN PS5000A_DOWNUP		
Arguments	operation, the type of waveform to be produced, specified by one of the following enumerated types:		
	PS5000A_ES_OFF, normal signal generator operation specified by wavetype.		

	PS5000A_WHITENOISE, PS5000A_PRBS,	the signal generator produces white noise and ignores all settings except pkToPk and offsetVoltage. produces a random bitstream with a bit rate specified by the start and stop frequency.
	I .	ne signal will be formed from the le, and dual index modes are possible.
	shots, see ps5000aSigGenE sweeps, see ps5000aSigGen triggerType, see ps5000as triggerSource, see ps500 extInThreshold, see ps50	BuiltIn SigGenBuiltIn OaSigGenBuiltIn
Returns	PICO_OK PICO_AWG_NOT_SUPPORTED PICO_POWER_SUPPLY_CONNE PICO_POWER_SUPPLY_NOT_O PICO_BUSY PICO_INVALID_HANDLE PICO_SIG_GEN_PARAM PICO_SHOTS_SWEEPS_WARNI PICO_NOT_RESPONDING PICO_WARNING_EXT_THRESH PICO_NO_SIGNAL_GENERATO PICO_SIGGEN_OFFSET_VOLT PICO_SIGGEN_PK_TO_PK PICO_SIGGEN_OUTPUT_OVER PICO_DRIVER_FUNCTION PICO_SIGGEN_WAVEFORM_SE	CONNECTED ONG OLD_CONFLICT OR CAGE CAGE


11.50.1 AWG index modes

The <u>arbitrary waveform generator</u> supports **single** and **dual** index modes to help you make the best use of the waveform buffer.

Single mode. The generator outputs the raw contents of the buffer repeatedly. This mode is the only one that can generate asymmetrical waveforms. You can also use this mode for symmetrical waveforms, but the dual mode makes more efficient use of the buffer memory.



Dual mode. The generator outputs the contents of the buffer from beginning to end, and then does a second pass in the reverse direction through the buffer. This allows you to specify only the first half of a waveform with twofold symmetry, such as a Gaussian function, and let the generator fill in the other half.



11.51 ps5000aSetSigGenBuiltIn

```
PICO_STATUS ps5000aSetSigGenBuiltIn
  int16_t
                                    handle,
  int32_t
                                    offsetVoltage,
  uint32_t
                                    pkToPk,
  PS5000A_WAVE_TYPE
                                    waveType,
                                    startFrequency,
  float
  float
                                    stopFrequency,
  float
                                    increment,
  float
                                    dwellTime,
  PS5000A_SWEEP_TYPE
                                    sweepType,
  PS5000A_EXTRA_OPERATIONS
                                    operation,
  uint32 t
                                    shots,
  uint32_t
                                    sweeps,
  PS5000A_SIGGEN_TRIG_TYPE
                                    triggerType,
  PS5000A_SIGGEN_TRIG_SOURCE
                                    triggerSource,
  int16_t
                                    extInThreshold
)
```

This function sets up the signal generator to produce a signal from a list of built-in waveforms. If different start and stop frequencies are specified, the device will sweep either up, down or up and down.

Applicability	All models	
Arguments	handle, the handle of the required device	
	offsetVoltage, the voltage offset, in microvolts, to be applied to the waveform	
	pkToPk, the peak-to-peak voltage, in microvolts, of the waveform signal. Note that if the signal voltages described by the combination of offsetVoltage and pkToPk extend outside the voltage range of the signal generator, the output waveform will be clipped.	
	waveType, the type of waveform to be generated. PS5000A_SINE sine wave PS5000A_SQUARE square wave PS5000A_TRIANGLE triangle wave PS5000A_DC_VOLTAGE DC voltage The following waveTypes apply to B models only. PS5000A_RAMP_UP rising sawtooth PS5000A_RAMP_DOWN falling sawtooth PS5000A_SINC sin (x)/x PS5000A_GAUSSIAN Gaussian PS5000A_HALF_SINE half (full-wave rectified) sine startFrequency, the frequency that the signal generator will initially produce. For allowable values see PS5000A_SINE_MAX_FREQUENCY and related values.	

	1	
Arguments	stopFrequency,	the frequency at which the sweep reverses direction or returns to the initial frequency
	increment,	the amount of frequency increase or decrease in sweep mode
	dwellTime,	the time for which the sweep stays at each frequency, in seconds
	sweepType,	whether the frequency will sweep from startFrequency to stopFrequency, or in the opposite direction, or repeatedly reverse direction. Use one of these constants: PS5000A_UP PS5000A_DOWN PS5000A_UPDOWN PS5000A_DOWNUP
	-	ype of waveform to be produced, specified by one of erated types (B models only):
	PS5000A_WHITE and ignores all s	wavetype. ENOISE, the signal generator produces white noise ettings except pkToPk and offsetVoltage. produces a random bitstream with a bit rate start and stop frequency.
	1PS5000A_M waveform to be p zero. PS5000A_SHOT_	quency as specified by sweeps IAX_SWEEPS_SHOTS: the number of cycles of the produced after a trigger event. sweeps must be SWEEP_TRIGGER_CONTINUOUS_RUN: start and after trigger occurs
	1PS5000A_MA the frequency aft shots must be: PS5000A_SHOT_	per of cycles specified by shots LX_SWEEPS_SHOTS: the number of times to sweep ter a trigger event, according to sweepType. zero. SWEEP_TRIGGER_CONTINUOUS_RUN: start a nue after trigger occurs
	triggerType, the generator:	e type of trigger that will be applied to the signal
	PS5000A_SIGGE PS5000A_SIGGE PS5000A_SIGGE PS5000A_SIGGE	IN_FALLING trigger on falling edge IN_GATE_HIGH run while trigger is high
Arguments	triggerSource,	the source that will trigger the signal generator.

	PS5000A_SIGGEN_NONE PS5000A_SIGGEN_SCOPE_TRIG PS5000A_SIGGEN_EXT_IN PS5000A_SIGGEN_SOFT_TRIG PS5000A_SIGGEN_TRIGGER_RAW	run without waiting for trigger use scope trigger use EXT input wait for software trigger provided by ps5000aSigGenSoftwareControl reserved
	If a trigger source other than P5000A_S either shots or sweeps, but not both extInThreshold, used to set trigger I	, must be non-zero.
		ever for external trigger.
Returns	PICO_OK PICO_BUSY PICO_POWER_SUPPLY_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTEI PICO_INVALID_HANDLE PICO_SIG_GEN_PARAM PICO_SHOTS_SWEEPS_WARNING PICO_NOT_RESPONDING PICO_WARNING_AUX_OUTPUT_CONFLIC PICO_WARNING_EXT_THRESHOLD_CONF PICO_NO_SIGNAL_GENERATOR PICO_SIGGEN_OFFSET_VOLTAGE PICO_SIGGEN_PK_TO_PK PICO_SIGGEN_OUTPUT_OVER_VOLTAGE PICO_SIGGEN_OUTPUT_OVER_VOLTAGE PICO_DRIVER_FUNCTION PICO_SIGGEN_WAVEFORM_SETUP_FAIR	CT FLICT
	PICO_NOT_RESPONDING	

11.52 ps5000aSetSigGenPropertiesArbitrary

```
PICO_STATUS ps5000aSetSigGenPropertiesArbitrary
  int16_t
                                handle,
  uint32_t
                                startDeltaPhase,
  uint32_t
                                stopDeltaPhase,
  uint32_t
                                deltaPhaseIncrement,
  uint32_t
                                dwellCount,
  PS5000A SWEEP TYPE
                                sweepType,
  uint32 t
                                shots,
  uint32_t
                                sweeps,
  PS5000A_SIGGEN_TRIG_TYPE
                                triggerType,
  PS5000A_SIGGEN_TRIG_SOURCE
                                triggerSource,
  int16_t
                                extInThreshold
)
```

This function reprograms the arbitrary waveform generator. All values can be reprogrammed while the signal generator is waiting for a trigger.

Arguments See ps5000aSetSigGenArbitrary() Returns PICO_OK if successful. PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO NO SIGNAL GENERATOR	Applicability	All modes
PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION	Arguments	See ps5000aSetSigGenArbitrary()
PICO_WARNING_AUX_OUTPUT_CONFLICT PICO_WARNING_EXT_THRESHOLD_CONFLICT PICO_SIGGEN_OFFSET_VOLTAGE PICO_SIGGEN_PK_TO_PK PICO_SIGGEN_PK_TO_PK PICO_SIGGEN_OFFSET_VOLTAGE PICO_SIG_GEN_PARAM PICO_SHOTS_SWEEPS_WARNING PICO_AWG_NOT_SUPPORTED PICO_BUSY PICO_SIGGEN_WAVEFORM_SETUP_FAILED PICO_NOT_RESPONDING PICO_POWER_SUPPLY_UNDERVOLTAGE PICO_POWER_SUPPLY_NOT_CONNECTED PICO_POWER_SUPPLY_NOT_CONNECTED		PICO_OK if successful. PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO_NO_SIGNAL_GENERATOR PICO_WARNING_AUX_OUTPUT_CONFLICT PICO_WARNING_EXT_THRESHOLD_CONFLICT PICO_SIGGEN_OFFSET_VOLTAGE PICO_SIGGEN_OUTPUT_OVER_VOLTAGE PICO_SIGGEN_PK_TO_PK PICO_SIGGEN_OFFSET_VOLTAGE PICO_SIG_GEN_PARAM PICO_SIG_GEN_PARAM PICO_SHOTS_SWEEPS_WARNING PICO_AWG_NOT_SUPPORTED PICO_BUSY PICO_SIGGEN_WAVEFORM_SETUP_FAILED PICO_NOT_RESPONDING PICO_POWER_SUPPLY_UNDERVOLTAGE PICO_POWER_SUPPLY_UNDERVOLTAGE

11.53 ps5000aSetSigGenPropertiesBuiltIn

```
PICO_STATUS ps5000aSetSigGenPropertiesBuiltIn
  int16_t
                              handle,
  double
                              startFrequency,
  double
                              stopFrequency,
  double
                              increment,
  double
                              dwellTime,
 PS5000A SWEEP TYPE
                              sweepType,
 uint32 t
                              shots,
 uint32_t
                              sweeps,
  PS5000A_SIGGEN_TRIG_TYPE triggerType,
 PS5000A_SIGGEN_TRIG_SOURCE triggerSource,
  int16_t
                              extInThreshold
)
```

This function reprograms the signal generator. Values can be changed while the signal generator is waiting for a trigger.

Applicability	All modes
Arguments	See ps5000aSetSigGenBuiltIn()
Returns	PICO_OK if successful. PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION PICO_NO_SIGNAL_GENERATOR PICO_SIG_GEN_PARAM PICO_WARNING_AUX_OUTPUT_CONFLICT PICO_WARNING_EXT_THRESHOLD_CONFLICT PICO_SIGGEN_DC_VOLTAGE_NOT_CONFIGURABLE PICO_BUSY PICO_SIGGEN_WAVEFORM_SETUP_FAILED PICO_NOT_RESPONDING PICO_POWER_SUPPLY_UNDERVOLTAGE PICO_USB3_0_DEVICE_NON_USB3_0_PORT PICO_POWER_SUPPLY_NOT_CONNECTED PICO_POWER_SUPPLY_CONNECTED

11.54 ps5000aSetSimpleTrigger

```
PICO_STATUS ps5000aSetSimpleTrigger
                                   handle,
  int16_t
  int16_t
                                   enable,
  PS5000A_CHANNEL
                                   source,
  int16_t
                                   threshold,
  PS5000A_THRESHOLD_DIRECTION
                                   direction,
  uint32 t
                                   delay,
                                   autoTrigger_ms
  int16_t
)
```

This function simplifies arming the trigger. It supports only the LEVEL trigger types and does not allow more than one channel to have a trigger applied to it. Any previous pulse width qualifier is cancelled.

Applicability	All modes
Arguments	handle: the handle of the required device.
	enable: zero to disable the trigger, any non-zero value to set the trigger.
	source: the channel on which to trigger.
	threshold: the ADC count at which the trigger will fire.
	direction: the direction in which the signal must move to cause a trigger. The following directions are supported: ABOVE, BELOW, RISING, FALLING and RISING_OR_FALLING.
	delay, the time between the trigger occurring and the first sample. For example, if delay=100 then the scope would wait 100 sample periods before sampling. At a $\underline{\text{timebase}}$ of 500 MS/s, or 2 ns per sample, the total delay would then be 100 x 2 ns = 200 ns. Range: 0 to $\underline{\text{MAX_DELAY_COUNT}}$.
	autoTrigger_ms: the number of milliseconds the device will wait if no trigger occurs. If this is set to zero, the scope device will wait indefinitely for a trigger.
<u>Returns</u>	PICO_OK PICO_INVALID_CHANNEL PICO_INVALID_PARAMETER PICO_MEMORY PICO_CONDITIONS PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_DRIVER_FUNCTION

11.55 ps5000aSetTriggerChannelConditions

This function sets up trigger conditions on the scope's inputs. The trigger is defined by one or more <u>PS5000A_TRIGGER_CONDITIONS</u> structures that are then ORed together. Each structure is itself the AND of the states of one or more of the inputs. This AND-OR logic allows you to create any possible Boolean function of the scope's inputs.

If complex triggering is not required, use ps5000aSetSimpleTrigger.

Applicability	All modes
Arguments	handle, the handle of the required device.
	* conditions, an array of PS5000A_TRIGGER_CONDITIONS structures specifying the conditions that should be applied to each channel. In the simplest case, the array consists of a single element. When there is more than one element, the overall trigger condition is the logical OR of all the elements.
	nConditions, the number of elements in the conditions array. If nConditions is zero then triggering is switched off.
Returns	PICO_OK PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_CONDITIONS PICO_MEMORY PICO_DRIVER_FUNCTION

11.55.1 PS5000A_TRIGGER_CONDITIONS structure

A structure of this type is passed to <u>ps5000aSetTriggerChannelConditions</u> in the conditions argument to specify the trigger conditions, and is defined as follows: -

```
typedef struct tPS5000ATriggerConditions
{
   PS5000A_TRIGGER_STATE channelA;
   PS5000A_TRIGGER_STATE channelB;
   PS5000A_TRIGGER_STATE channelC;
   PS5000A_TRIGGER_STATE channelD;
   PS5000A_TRIGGER_STATE external;
   PS5000A_TRIGGER_STATE aux;
   PS5000A_TRIGGER_STATE pulseWidthQualifier;
}
```

Each structure is the logical AND of the states of the scope's inputs. The ps5000aSetTriggerChannelConditions function can OR together a number of these structures to produce the final trigger condition, which can be any possible Boolean function of the scope's inputs.

The structure is byte-aligned. In C++, for example, you should specify this using the #pragma pack() instruction.

```
channelA, channelB, channelC, channelD, external, pulseWidthQualifier: the type of condition that should be applied to each channel. Use these constants:

PS5000A_CONDITION_DONT_CARE

PS5000A_CONDITION_TRUE

PS5000A_CONDITION_FALSE

The channels that are set to PS5000A_CONDITION_TRUE or PS5000A_CONDITION_FALSE must all meet their conditions simultaneously to produce a trigger. Channels set to PS5000A_CONDITION_DONT_CARE are ignored.

aux: not used
```

11.56 ps5000aSetTriggerChannelDirections

```
PICO_STATUS ps5000aSetTriggerChannelDirections (

int16_t handle,
    PS5000A_THRESHOLD_DIRECTION channelA,
    PS5000A_THRESHOLD_DIRECTION channelB,
    PS5000A_THRESHOLD_DIRECTION channelC;
    PS5000A_THRESHOLD_DIRECTION channelD;
    PS5000A_THRESHOLD_DIRECTION ext,
    PS5000A_THRESHOLD_DIRECTION aux
)
```

This function sets the direction of the trigger for each channel.

Applicability	All modes
Arguments	handle, the handle of the required device
	channelA, channelB, channelC, channelD, ext, the direction in which the signal must pass through the threshold to activate the trigger. See the <u>table</u> below for allowable values. If using a level trigger in conjunction with a pulse-width trigger, see the description of the direction argument to <u>ps5000aSetPulseWidthQualifier</u> for more information.
	aux: not used
Returns	PICO_OK
	PICO_INVALID_HANDLE PICO USER CALLBACK
	PICO_INVALID_PARAMETER

PS5000A_THRESHOLD_DIRECTION constants

PS5000A_ABOVE	for gated triggers: above the upper threshold
PS5000A_ABOVE_LOWER	for gated triggers: above the lower threshold
PS5000A_BELOW	for gated triggers: below the upper threshold
PS5000A_BELOW_LOWER	for gated triggers: below the lower threshold
PS5000A_RISING	for threshold triggers: rising edge, using upper threshold
PS5000A_RISING_LOWER	for threshold triggers: rising edge, using lower threshold
PS5000A_FALLING	for threshold triggers: falling edge, using upper threshold
PS5000A_FALLING_LOWER	for threshold triggers: falling edge, using lower threshold
PS5000A_RISING_OR_FALLING	for threshold triggers: either edge
PS5000A_INSIDE	for window-qualified triggers: inside window
PS5000A_OUTSIDE	for window-qualified triggers: outside window
PS5000A_ENTER	for window triggers: entering the window
PS5000A_EXIT	for window triggers: leaving the window
PS5000A_ENTER_OR_EXIT	for window triggers: either entering or leaving the window
PS5000A_POSITIVE_RUNT	for window-qualified triggers
PS5000A_NEGATIVE_RUNT	for window-qualified triggers
PS5000A_NONE	no trigger

11.57 ps5000aSetTriggerChannelProperties

This function is used to enable or disable triggering and set its parameters.

Applicability	All modes
Arguments	handle, the handle of the required device.
	* channelProperties, a pointer to an array of PS5000A_TRIGGER_CHANNEL_PROPERTIES structures describing the requested properties. The array can contain a single element describing the properties of one channel, or a number of elements describing several channels. If NULL is passed, triggering is switched off.
	nChannelProperties, the size of the channelProperties array. If zero, triggering is switched off.
	auxOutputEnable: not used
	autoTriggerMilliseconds, the time in milliseconds for which the scope device will wait before collecting data if no trigger event occurs. If this is set to zero, the scope device will wait indefinitely for a
	trigger.
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_TRIGGER_ERROR PICO_MEMORY PICO_INVALID_TRIGGER_PROPERTY PICO DRIVER FUNCTION
	PICO_INVALID_PARAMETER

11.57.1 PS5000A_TRIGGER_CHANNEL_PROPERTIES structure

A structure of this type is passed to <u>ps5000aSetTriggerChannelProperties</u> in the channelProperties argument to specify the trigger mechanism, and is defined as follows: -

The structure is byte-aligned. In C++, for example, you should specify this using the #pragma pack() instruction.

Elements

thresholdUpper, the upper threshold at which the trigger must fire. This is scaled in 16-bit <u>ADC counts</u> at the currently selected range for that channel.

thresholdUpperHysteresis, the hysteresis by which the trigger must exceed the upper threshold before it will fire. It is scaled in 16-bit counts.

thresholdLower, the lower threshold at which the trigger must fire. This is scaled in 16-bit <u>ADC counts</u> at the currently selected range for that channel.

thresholdLowerHysteresis, the hysteresis by which the trigger must exceed the lower threshold before it will fire. It is scaled in 16-bit counts.

channel, the channel to which the properties apply. This can be one of the four input channels listed under ps5000aSetChannel, or PS5000A_TRIGGER_AUX for the AUX input.

thresholdMode, either a level or window trigger. Use one of these constants: -

PS5000A_LEVEL PS5000A_WINDOW

11.58 ps5000aSetTriggerDelay

```
PICO_STATUS ps5000aSetTriggerDelay
(
  int16_t handle,
  uint32_t delay
)
```

This function sets the post-trigger delay, which causes capture to start a defined time after the trigger event.

Applicability	All modes
Arguments	handle, the handle of the required device
	delay, the time between the trigger occurring and the first sample. For example, if $delay=100$ then the scope would wait 100 sample periods before sampling. At a <u>timebase</u> of 500 MS/s, or 2 ns per sample, the total delay would then be $100 \times 2 \text{ ns} = 200 \text{ ns}$. Range: 0 to MAX_DELAY_COUNT
Returns	PICO_OK PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_DRIVER_FUNCTION

11.59 ps5000aSigGenArbitraryMinMaxValues

This function returns the range of possible sample values and waveform buffer sizes that can be supplied to $\underline{ps5000aSetSignGenArbitrary()}$ for setting up the arbitrary waveform generator (\underline{AWG}). These values vary between different models in the PicoScope 5000 Series.

Applicability	All models with AWG
Arguments	handle, the handle of the required device.
	minArbitraryWaveformValue, on exit, the lowest sample value allowed in the arbitraryWaveform buffer supplied to ps5000aSetSignGenArbitrary().
	maxArbitraryWaveformValue, on exit, the highest sample value allowed in the arbitraryWaveform buffer supplied to ps5000aSetSignGenArbitrary() .
	minArbitraryWaveformSize, on exit, the minimum value allowed for the arbitraryWaveformSize argument supplied to ps5000aSetSignGenArbitrary().
	maxArbitraryWaveformSize, on exit, the maximum value allowed for the arbitraryWaveformSize argument supplied to ps5000aSetSignGenArbitrary().
<u>Returns</u>	PICO_OK
	PICO_NOT_SUPPORTED_BY_THIS_DEVICE, if the device does not have an arbitrary waveform generator.
	PICO_NULL_PARAMETER, if all the parameter pointers are NULL. PICO_INVALID_HANDLE PICO_DRIVER_FUNCTION

11.60 ps5000aSigGenFrequencyToPhase

```
PICO_STATUS ps5000aSigGenFrequencyToPhase (

int16_t handle,
double frequency,
PS6000_INDEX_MODE indexMode,
uint32_t bufferLength,
uint32_t * phase
)
```

This function converts a frequency to a phase count for use with the arbitrary waveform generator (AWG). The value returned depends on the length of the buffer, the index mode passed and the device model. The phase count can then be sent to the driver through ps5000aSetSigGenArbitrary() or ps5000aSetSigGenPropertiesArbitrary().

Applicability	All models with AWG
Arguments	handle, the handle of the required device.
	frequency, the required AWG output frequency.
	indexMode, see <u>AWG index modes</u> .
	bufferLength, the number of samples in the AWG buffer.
	phase, on exit, the deltaPhase argument to be sent to the AWG setup function
Returns	PICO_OK
	PICO_NOT_SUPPORTED_BY_THIS_DEVICE, if the device does not
	have an AWG.
	PICO_SIGGEN_FREQUENCY_OUT_OF_RANGE, if the frequency is out
	of range.
	PICO_NULL_PARAMETER, if phase is a NULL pointer.
	PICO_SIG_GEN_PARAM, if indexMode or bufferLength is out of
	range. PICO_INVALID_HANDLE
	PICO_DRIVER_FUNCTION

11.61 ps5000aSigGenSoftwareControl

```
PICO_STATUS ps5000aSigGenSoftwareControl
(
  int16_t handle,
  int16_t state
)
```

This function causes a trigger event, or starts and stops gating. It is used when the signal generator is set to SIGGEN_SOFT_TRIG.

Gating occurs when the trigger type is set to either $PS5000A_SIGGEN_GATE_HIGH$ or $PS5000A_SIGGEN_GATE_LOW$. With other trigger types, calling this function causes the signal generator to trigger immediately.

Applicability	Use with <u>ps5000aSetSigGenBuiltIn</u> or <u>ps5000aSetSigGenArbitrary</u> .
Arguments	handle, the handle of the required device
	state, sets the trigger gate high or low: 0: gate low condition <> 0: gate high condition Ignored if trigger type is not set to either PS5000A_SIGGEN_GATE_HIGH or PS5000A_SIGGEN_GATE_LOW.
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_NO_SIGNAL_GENERATOR PICO_SIGGEN_TRIGGER_SOURCE PICO_DRIVER_FUNCTION PICO_NOT_RESPONDING

11.62 ps5000aStop

```
PICO_STATUS ps5000aStop
(
  int16_t handle
)
```

This function stops the scope device from sampling data. If this function is called before a trigger event occurs, the oscilloscope may not contain valid data.

Always call this function after the end of a capture to ensure that the scope is ready for the next capture.

Applicability	All modes
Arguments	handle, the handle of the required device.
<u>Returns</u>	PICO_OK PICO_INVALID_HANDLE PICO_USER_CALLBACK PICO_DRIVER_FUNCTION

11.63 ps5000aStreamingReady (callback)

This <u>callback</u> function is part of your application. You register it with the driver using <u>ps5000aGetStreamingLatestValues</u>, and the driver calls it back when streaming-mode data is ready. You can then download the data using the <u>ps5000aGetValuesAsync</u> function.

Your callback function should do nothing more than copy the data to another buffer within your application. To maintain the best application performance, the function should return as quickly as possible without attempting to process or display the data.

Applicability	Streaming mode only
Arguments	handle, the handle of the device returning the samples.
	noOfSamples, the number of samples to collect.
	$\verb startIndex , an index to the first valid sample in the buffer. This is the buffer that was previously passed to \verb ps5000aSetDataBuffer . $
	overflow, returns a set of flags that indicate whether an overvoltage has occurred on any of the channels. It is a bit pattern with bit 0 denoting Channel A.
	triggerAt, an index to the buffer indicating the location of the trigger point relative to startIndex. This parameter is valid only when triggered is non-zero.
	triggered, a flag indicating whether a trigger occurred. If non-zero, a trigger occurred at the location indicated by triggerAt.
	autoStop, the flag that was set in the call to ps5000aRunStreaming .
	* pParameter, a void pointer passed from ps5000aGetStreamingLatestValues. The callback function can write to this location to send any data, such as a status flag, back to the application.
Returns	nothing

104 Programming examples

12 Programming examples

Your PicoScope SDK installation includes programming examples in various languages and development environments.

13 Driver status codes

Every function in the ps5000a driver returns a **driver status code** from the following list of PICO_STATUS values. These definitions can also be found in the file picoStatus.h, which is included in the ps5000a SDK. Not all codes apply to the ps5000a SDK.

Code (hex)	Symbol and meaning
00	PICO_OK
	The PicoScope is functioning correctly
01	PICO_MAX_UNITS_OPENED
	An attempt has been made to open more than PS5000A_MAX_UNITS
02	PICO MEMORY FAIL
	Not enough memory could be allocated on the host machine
03	PICO_NOT_FOUND
	No PicoScope could be found
04	PICO FW FAIL
	Unable to download firmware
05	PICO_OPEN_OPERATION_IN_PROGRESS
06	PICO_OPERATION_FAILED
07	PICO NOT RESPONDING
0 /	The PicoScope is not responding to commands from the PC
08	PICO_CONFIG_FAIL
	The configuration information in the PicoScope has become corrupt or is missing
09	PICO KERNEL DRIVER TOO OLD
	The picopp.sys file is too old to be used with the device driver
0A	
UA	PICO_EEPROM_CORRUPT The FERROM has become corrupt so the device will use a default cetting
0B	The EEPROM has become corrupt, so the device will use a default setting
ОБ	PICO_OS_NOT_SUPPORTED The appraising system on the PC is not supported by this driver
0C	The operating system on the PC is not supported by this driver PICO INVALID HANDLE
000	There is no device with the handle value passed
0D	PICO INVALID PARAMETER
OD	A parameter value is not valid
0E	PICO_INVALID_TIMEBASE
	The timebase is not supported or is invalid
OF	PICO_INVALID_VOLTAGE_RANGE
01	The voltage range is not supported or is invalid
10	PICO INVALID CHANNEL
- 0	The channel number is not valid on this device or no channels have been set
11	PICO_INVALID_TRIGGER_CHANNEL
	The channel set for a trigger is not available on this device
12	PICO_INVALID_CONDITION_CHANNEL
	The channel set for a condition is not available on this device
13	PICO NO SIGNAL GENERATOR
	The device does not have a signal generator
14	PICO_STREAMING_FAILED
	Streaming has failed to start or has stopped without user request
15	PICO_BLOCK_MODE_FAILED
'-	Block failed to start - a parameter may have been set wrongly
16	PICO NULL PARAMETER
	A parameter that was required is NULL
18	PICO_DATA_NOT_AVAILABLE
-0	No data is available from a run block call
	no data is available from a ran block can

106 Driver status codes

19	PICO_STRING_BUFFER_TOO_SMALL
	The buffer passed for the information was too small
1A	PICO_ETS_NOT_SUPPORTED
	ETS is not supported on this device
1В	PICO_AUTO_TRIGGER_TIME_TOO_SHORT
	The auto trigger time is less than the time it will take to collect the pre-trigger data
1C	PICO_BUFFER_STALL
	The collection of data has stalled as unread data would be overwritten
1D	PICO_TOO_MANY_SAMPLES
	Number of samples requested is more than available in the current memory segment
1E	PICO_TOO_MANY_SEGMENTS
	Not possible to create number of segments requested
1F	PICO_PULSE_WIDTH_QUALIFIER
	A null pointer has been passed in the trigger function or one of the parameters is out
	of range
20	PICO_DELAY
	One or more of the hold-off parameters are out of range
21	PICO_SOURCE_DETAILS
	One or more of the source details are incorrect
22	PICO_CONDITIONS
	One or more of the conditions are incorrect
23	The driver's thread is currently in the ps5000aReady callback function and therefore
	the action cannot be carried out
24	PICO_DEVICE_SAMPLING
	An attempt is being made to get stored data while streaming. Either stop streaming by
	calling ps5000aStop, or use ps5000aGetStreamingLatestValues.
25	PICO_NO_SAMPLES_AVAILABLE
	because a run has not been completed
26	PICO_SEGMENT_OUT_OF_RANGE
	The memory index is out of range
27	PICO_BUSY
	Data cannot be returned yet
28	PICO_STARTINDEX_INVALID
	The start time to get stored data is out of range
29	PICO_INVALID_INFO
	The information number requested is not a valid number
2A	PICO_INFO_UNAVAILABLE
	The handle is invalid so no information is available about the device. Only
0-	PICO_DRIVER_VERSION is available.
2В	PICO_INVALID_SAMPLE_INTERVAL
0.5	The sample interval selected for streaming is out of range
2C	PICO_TRIGGER_ERROR
2D	PICO_MEMORY
	Driver cannot allocate memory
35	PICO_SIGGEN_OUTPUT_OVER_VOLTAGE
	The combined peak to peak voltage and the analog offset voltage exceed the allowable
	voltage the signal generator can produce
36	PICO_DELAY_NULL
	NULL pointer passed as delay parameter
37	PICO_INVALID_BUFFER
	The buffers for overview data have not been set while streaming
38	PICO_SIGGEN_OFFSET_VOLTAGE
	The analog offset voltage is out of range
39	PICO_SIGGEN_PK_TO_PK
	The analog peak to peak voltage is out of range
3A	PICO_CANCELLED

	A black collection has been cancelled
3B	A block collection has been cancelled PICO SEGMENT NOT USED
3B	
20	The segment index is not currently being used
3C	PICO_INVALID_CALL The wrong Cet/alues function has been called for the callection made in use
217	The wrong GetValues function has been called for the collection mode in use
3F	PICO_NOT_USED
1.0	The function is not available
40	PICO_INVALID_SAMPLERATIO
	The <u>aggregation</u> ratio requested is out of range
41	PICO_INVALID_STATE
	Device is in an invalid state
42	PICO_NOT_ENOUGH_SEGMENTS
	The number of segments allocated is fewer than the number of captures requested
43	PICO_DRIVER_FUNCTION
	You called a driver function while another driver function was still being processed
	PICO_RESERVED
45	PICO_INVALID_COUPLING
	An invalid coupling type was specified in <u>ps5000aSetChannel</u>
46	PICO_BUFFERS_NOT_SET
- 0	An attempt was made to get data before a data buffer was defined
47	PICO RATIO MODE NOT SUPPORTED
1	The selected downsampling mode (used for data reduction) is not allowed
49	PICO_INVALID_TRIGGER_PROPERTY
49	An invalid parameter was passed to ps5000aSetTriggerChannelProperties
4A	PICO_INTERFACE_NOT_CONNECTED
TA.	The driver was unable to contact the oscilloscope
4 D	PICO_SIGGEN_WAVEFORM_SETUP_FAILED
4D	
4.00	A problem occurred in ps5000aSetSigGenBuiltIn or ps5000aSetSigGenArbitrary
4E	PICO_FPGA_FAIL
1 =	FPGA not successfully set up
4F	PICO_POWER_MANAGER
50	PICO_INVALID_ANALOGUE_OFFSET
50	An impossible analogue offset value was specified in ps5000aSetChannel
51	PICO_PLL_LOCK_FAILED
	Unable to configure the PicoScope
52	PICO_ANALOG_BOARD
	The oscilloscope's analog board is not detected, or is not connected to the digital
	board
53	PICO_CONFIG_FAIL_AWG
	Unable to configure the signal generator
54	PICO_INITIALISE_FPGA
	The FPGA cannot be initialized, so unit cannot be opened
56	PICO_EXTERNAL_FREQUENCY_INVALID
	The frequency for the external clock is not within ±5% of the stated value
57	PICO_CLOCK_CHANGE_ERROR
	The FPGA could not lock the clock signal
58	PICO_TRIGGER_AND_EXTERNAL_CLOCK_CLASH
- -	You are trying to configure the AUX input as both a trigger and a reference clock
59	PICO_PWO_AND_EXTERNAL_CLOCK_CLASH
	You are trying to configure the AUX input as both a pulse width qualifier and a
	reference clock
5A	PICO_UNABLE_TO_OPEN_SCALING_FILE
	The scaling file set can not be opened
5B	PICO_MEMORY_CLOCK_FREQUENCY
עכ	The frequency of the memory is reporting incorrectly
5C	PICO_I2C_NOT_RESPONDING
JC	LICOTIOITEDECINDING

Driver status codes

	The I2C that is being actioned is not responding to requests
5D	PICO_NO_CAPTURES_AVAILABLE
لاد	There are no captures available and therefore no data can be returned
5E	PICO_NOT_USED_IN_THIS_CAPTURE_MODE
75	The capture mode the device is currently running in does not support the current
	request
103	PICO_GET_DATA_ACTIVE
	Reserved
104	PICO_IP_NETWORKED
	The device is currently connected via the IP Network socket and thus the call made is
	not supported
105	PICO_INVALID_IP_ADDRESS
	An IP address that is not correct has been passed to the driver
106	PICO_IPSOCKET_FAILED
	The IP socket has failed
107	PICO_IPSOCKET_TIMEDOUT
	The IP socket has timed out
108	PICO_SETTINGS_FAILED
1.00	The settings requested have failed to be set
109	PICO_NETWORK_FAILED
107	The network connection has failed
10A	PICO_WS2_32_DLL_NOT_LOADED Unable to load the WS2 DLL
100	
10B	PICO_INVALID_IP_PORT The IP port is invalid.
10C	The IP port is invalid
100	PICO_COUPLING_NOT_SUPPORTED The type of coupling requested is not supported on the opened device
10D	PICO_BANDWIDTH_NOT_SUPPORTED
	Bandwidth limit is not supported on the opened device
10E	PICO_INVALID_BANDWIDTH
105	The value requested for the bandwidth limit is out of range
10F	PICO AWG NOT SUPPORTED
- 01	The arbitrary waveform generator is not supported by the opened device
110	PICO ETS NOT RUNNING
	Data has been requested with ETS mode set but run block has not been called, or stop
	has been called
111	PICO_SIG_GEN_WHITENOISE_NOT_SUPPORTED
	White noise is not supported on the opened device
112	PICO_SIG_GEN_WAVETYPE_NOT_SUPPORTED
	The wave type requested is not supported by the opened device
116	PICO_SIG_GEN_PRBS_NOT_SUPPORTED
	Siggen does not generate pseudo-random binary sequence
117	PICO_ETS_NOT_AVAILABLE_WITH_LOGIC_CHANNELS
	When a digital port is enabled, ETS sample mode is not available for use
118	PICO_WARNING_REPEAT_VALUE
	Not applicable to this device
119	PICO_POWER_SUPPLY_CONNECTED
	4-channel only - the DC power supply is connected
11A	PICO_POWER_SUPPLY_NOT_CONNECTED
11-	4-channel only - the DC power supply isn't connected
11B	PICO_POWER_SUPPLY_REQUEST_INVALID
110	Incorrect power mode passed for current power source
11C	PICO_POWER_SUPPLY_UNDERVOLTAGE The supply veltage from the USB source is too low
11D	The supply voltage from the USB source is too low PICO_CAPTURING_DATA
דדח	The device is currently busy capturing data
	The device is currently busy capturing data

11E	PICO_USB3_0_DEVICE_NON_USB3_0_PORT				
	A Pico USB 3.0 device has been connected to a non-USB 3.0 port				
11F	PICO_NOT_SUPPORTED_BY_THIS_DEVICE				
	A function has been called that is not supported by the current device variant				
120 PICO_INVALID_DEVICE_RESOLUTION The device resolution is invalid (out of range)					
				121	PICO_INVALID_NO_CHANNELS_FOR_RESOLUTION
	The number of channels which can be enabled is limited in 15 and 16-bit modes				
122	PICO_CHANNEL_DISABLED_DUE_TO_USB_POWERED				
	USB power not sufficient to power all channels				
	osb power not sufficient to power an channels				

14 Enumerated types and constants

The enumerated types used in the PicoScope 5000 (A API) SDK are defined in the file ps5000aApi.h. We recommend that you refer to these constants by name unless your programming language allows only numerical values.

15 Numeric data types

Here is a list of the sizes and ranges of the numeric data types used in the PicoScope 5000 A API.

Туре	Bits	Signed or unsigned?
int16_t	16	signed
enum	32	enumerated
int32_t	32	signed
uint32_t	32	unsigned
float	32	signed (IEEE 754)
int64	64	signed

112 Glossary

16 Glossary

AC/DC control. Each channel can be set to either AC coupling or DC coupling. With DC coupling, the voltage displayed on the screen is equal to the true voltage of the signal. With AC coupling, any DC component of the signal is filtered out, leaving only the variations in the signal (the AC component).

Aggregation. The PicoScope 5000 driver can use a method called aggregation to reduce the amount of data your application needs to process. This means that for every block of consecutive samples, it stores only the minimum and maximum values. You can set the number of samples in each block, called the aggregation parameter, when you call ps5000aRunStreaming for real-time capture, and when you call ps5000aGetStreamingLatestValuesto obtain post-processed data.

Aliasing. An effect that can cause digital oscilloscopes to display fast-moving waveforms incorrectly, by showing spurious low-frequency signals ("aliases") that do not exist in the input. To avoid this problem, choose a sampling rate that is at least twice the frequency of the fastest-changing input signal.

Analog bandwidth. All oscilloscopes have an upper limit to the range of frequencies at which they can measure accurately. The analog bandwidth of an oscilloscope is defined as the frequency at which a displayed sine wave has half the power of the input sine wave (or, equivalently, about 71% of the amplitude).

Block mode. A sampling mode in which the computer prompts the oscilloscope to collect a block of data into its internal memory before stopping the oscilloscope and transferring the whole block into computer memory. This mode of operation is effective when the input signal being sampled is high frequency. Note: To avoid <u>aliasing</u> effects, the maximum input frequency must be less than half the sampling rate.

Buffer size. The size, in samples, of the oscilloscope buffer memory. The buffer memory is used by the oscilloscope to temporarily store data before transferring it to the PC.

Callback. A mechanism that the PicoScope 5000 driver uses to communicate asynchronously with your application. At design time, you add a function (a *callback* function) to your application to deal with captured data. At run time, when you request captured data from the driver, you also pass it a pointer to your function. The driver then returns control to your application, allowing it to perform other tasks until the data is ready. When this happens, the driver calls your function in a new thread to signal that the data is ready. It is then up to your function to communicate this fact to the rest of your application.

ETS. Equivalent Time Sampling. ETS constructs a picture of a repetitive signal by accumulating information over many similar wave cycles. This means the oscilloscope can capture fast-repeating signals that have a higher frequency than the maximum sampling rate. Note: ETS should not be used for one-shot or non-repetitive signals.

External trigger. This is the BNC socket marked **EXT** or **Ext**. It can be used to start a data collection run but cannot be used to record data.

Flexible power. The 5000 Series oscilloscopes can be powered by either the two-headed USB cable supplied for obtaining power from two USB ports, or a single USB port and the AC adapter (included with 4-channel models only).

Maximum sampling rate. A figure indicating the maximum number of samples the oscilloscope is capable of acquiring per second. Maximum sample rates are given in MS/s (megasamples per second). The higher the sampling capability of the oscilloscope, the more accurate the representation of the high frequencies in a fast signal.

Overvoltage. Any input voltage to the oscilloscope must not exceed the overvoltage limit, measured with respect to ground, otherwise the oscilloscope may be permanently damaged.

PC Oscilloscope. A measuring instrument consisting of a Pico Technology scope device and the PicoScope software. It provides all the functions of a bench-top oscilloscope without the cost of a display, hard disk, network adapter and other components that your PC already has.

PicoScope software. This is a software product that accompanies all our oscilloscopes. It turns your PC into an oscilloscope, spectrum analyzer, and meter display.

Signal generator. This is a feature of some oscilloscopes which allows a signal to be generated without an external input device being present. The signal generator output is the BNC socket marked **GEN** or **Gen** on the oscilloscope. If you connect a BNC cable between this and one of the channel inputs, you can send a signal into one of the channels. It can generate a sine, square or triangle wave that can be swept back and forth.

Spectrum analyzer. An instrument that measures the energy content of a signal in each of a large number of frequency bands. It displays the result as a graph of energy (on the vertical axis) against frequency (on the horizontal axis). The PicoScope software includes a spectrum analyzer.

Streaming mode. A sampling mode in which the oscilloscope samples data and returns it to the computer in an unbroken stream. This mode of operation is effective when the input signal being sampled contains only low frequencies.

Timebase. The timebase controls the time interval across the scope display. There are ten divisions across the screen and the timebase is specified in units of time per division, so the total time interval is ten times the timebase.

- **USB 1.1.** USB (Universal Serial Bus) is a standard port that enables you to connect external devices to PCs. A typical USB 1.1 port supports a data transfer rate of 12 Mbps (12 megabits per second), much faster than an RS232 port.
- **USB 2.0.** A typical USB 2.0 port supports a data transfer rate that is 40 times faster than USB 1.1. USB 2.0 is backwards-compatible with USB 1.1.
- **USB 3.0.** A typical USB 3.0 port supports a data transfer rate that is 10 times faster than USB 2.0. USB 3.0 is backwards-compatible with USB 2.0 and USB 1.1.

Vertical resolution. A value, in bits, indicating the degree of precision with which the oscilloscope can turn input voltages into digital values. Calculation techniques can improve the effective resolution.

Voltage range. The voltage range is the difference between the maximum and minimum voltages that can be accurately captured by the oscilloscope.



Index	Downsampling 10, 47 maximum ratio 36 modes 48 Driver 5
A	status codes 105
AC/DC coupling 71, 112 Access 3	E
ADC count 58, 60 Aggregation 19 Aliasing 112 Analog bandwidth 112 Analog offset 33, 71 API function calls 24 Arbitrary waveform generator 83, 85 buffer lengths 99 sample values 99	Enabling channels 71 Enumerated types 110 Enumerating oscilloscopes 31 ETS overview 17 setting time buffers 77, 78 setting up 76 using 18
В	F
Bandwidth limiter 71 Block mode 8, 9, 10, 11, 112 asynchronous call 11 callback 26 polling status 56 running 66 Buffer size 112	Fitness for purpose 3 Functions overview 24 ps5000aBlockReady 26 ps5000aChangePowerSource 27 ps5000aCloseUnit 28 ps5000aCurrentPowerSource 29 ps5000aDataReady 30
С	ps5000aEnumerateUnits 31 ps5000aFlashLed 32
Callback function 9 block mode 26 definition 30 ETS mode 17 streaming mode 103 Channels enabling 71 settings 71 Closing units 28 Common-mode voltage 112 Communication 65 Connection 65 Constants 110 Copyright 3 Coupling type, setting 71	ps5000aGetAnalogueOffset 33 ps5000aGetChannelInformation 34 ps5000aGetDeviceResolution 35 ps5000aGetMaxDownSampleRatio 36 ps5000aGetMaxSegments 37 ps5000aGetNoOfCaptures 38, 39 ps5000aGetStreamingLatestValues 40 ps5000aGetTimebase 21, 41 ps5000aGetTimebase2 42 ps5000aGetTriggerTimeOffset 43 ps5000aGetTriggerTimeOffset 44 ps5000aGetUnitInfo 45 ps5000aGetValues 11, 47 ps5000aGetValuesAsync 11, 49 ps5000aGetValuesBulk 50 ps5000aGetValuesOverlapped 51
D	ps5000aGetValuesOverlapped 51 ps5000aGetValuesOverlappedBulk 52 ps5000aGetValuesTriggerTimeOffsetBulk 53
Data acquisition 19 Data buffers declaring 73 declaring, aggregation mode 74 Data retention 10	ps5000aGetValuesTriggerTimeOffsetBulk64 55 ps5000aIsReady 56 ps5000aIsTriggerOrPulseWidthQualifierEnabled 57 ps5000aMaximumValue 7, 58

116 Index

Functions				
ps5000aMemorySegments 59	M			
ps5000aMinimumValue 7, 60				
ps5000aNoOfStreamingValues 61	Memory in scope 10			
ps5000aOpenUnit 62	Mission-critical applications 3			
ps5000aOpenUnitAsync 63	Multi-unit operation 23			
ps5000aOpenUnitProgress 64	N.I.			
ps5000aPingUnit 65	N			
ps5000aRunBlock 66	Numeric data types 111			
ps5000aRunStreaming 68				
ps5000aSetChannel 7, 71	0			
ps5000aSetDataBuffer 73	· ·			
ps5000aSetDataBuffers 74	One-shot signals 17			
ps5000aSetDeviceResolution 75	Opening a unit 62			
ps5000aSetEts 17, 76	checking progress 64			
ps5000aSetEtsTimeBuffer 77	without blocking 63			
ps5000aSetEtsTimeBuffers 78	_			
ps5000aSetNoOfCaptures 79	P			
ps5000aSetPulseWidthQualifier 80	PC Oscilloscope 1, 112			
ps5000aSetSigGenArbitrary 83	PC requirements 2			
ps5000aSetSigGenBuiltIn 87	PICO_STATUS enum type 105			
ps5000aSetSigGenPropertiesArbitrary 90	PicoScope 5000 Series 1			
ps5000aSetSigGenPropertiesBuiltIn 91	PicoScope software 1, 5, 105, 112			
ps5000aSetSimpleTrigger 8, 92	Power options			
ps5000aSetTriggerChannelConditions 8, 93	flexible power options 22			
ps5000aSetTriggerChannelDirections 8, 95	Power source 27, 29			
ps5000aSetTriggerChannelProperties 8, 96	ps5000a.dll 5			
ps5000aSetTriggerDelay 98	PS5000A_CONDITION_ constants 82			
ps5000aSigGenArbitraryMinMaxValues 99	PS5000A_LEVEL constant 97			
ps5000aSigGenFrequencyToPhase 100	PS5000A_PWQ_CONDITIONS structure 82			
ps5000aSigGenSoftwareControl 101	PS5000A_RATIO_MODE_AGGREGATE 48			
ps5000aStop 11, 102	PS5000A_RATIO_MODE_AVERAGE 48			
ps5000aStreamingReady 103	PS5000A_RATIO_MODE_AVERAGE 48			
	PS5000A_TIME_UNITS constant 43, 44			
H	PS5000A_TRIGGER_CHANNEL_PROPERTIES			
Hysteresis 97	structure 97			
11/3(c)(3)3	PS5000A_TRIGGER_CONDITION constants 94			
	PS5000A_TRIGGER_CONDITIONS 93			
	PS5000A_TRIGGER_CONDITIONS structure 94			
Index modes 85	PS5000A_WINDOW constant 97			
Input range, selecting 71	Pulse-width qualifier 80			
Intended use 1	conditions 82			
	requesting status 57			
_	R			
LED Grahim 22				
flashing 32	Ranges 34			
Legal information 3	Rapid block mode 9, 12, 38, 39			
Liability 3	aggregation 16			
	no aggregation 14			
	setting number of captures 79			
	Pecolution			

Resolution PS5000A_DEVICE_RESOLUTION	62	requesting status 57 setting up 92	
vertical 112 Retrieving data 47, 49 block mode, deferred 51		stability 17 time offset 43, 44	
rapid block mode 50		U	
rapid block mode, deferred 52 stored 20 streaming mode 40		Unit information, reading 45 Upgrades 3	
Retrieving times rapid block mode 53, 55		Usage 3 USB 1, 2, 6, 112 hub 23	
S		V	
Sampling rate 112 maximum 10 Scaling 7 Segmented memory 10, 11, 19		V Viruses 3 Voltage range 7, 112 selecting 71	
ps5000aMemorySegments 59		VA /	
Serial numbers 31		VV	
Setup time 10 Signal generator arbitrary waveforms 83 built-in waveforms 87 calculating phase 100 software trigger 101 Spectrum analyzer 1, 112 Status codes 105 Stopping sampling 102 Streaming mode 9, 19, 112 callback 103 getting number of samples 61 retrieving data 40 running 68 using 19 Support 3		WinUsb.sys 5	
T			
Threshold voltage 8 Time buffers setting for ETS 77, 78			
Timebase 21, 112 calculating 41, 42			
Trademarks 3			
Trigger 8 channel properties 96 conditions 93, 94 delay 98 directions 95			
pulse-width qualifier 80 pulse-width qualifier conditions	82		



 ${\sf UK}\ head quarters$

Pico Technology James House Colmworth Business Park St. Neots Cambridgeshire PE19 8YP United Kingdom

Tel: +44 (0) 1480 396 395 Fax: +44 (0) 1480 396 296

sales@picotech.com support@picotech.com

www.picotech.com

USA headquarters

Pico Technology 320 N Glenwood Blvd Tyler Texas 75702 United States of America

Tel: +1 800 591 2796 Fax: +1 620 272 0981

ps5000apg.en r2 28/05/2015 Copyright © 2013-2015 Pico Technology Limited. All rights reserved.